

# The **tocloft** package<sup>\*</sup>

Peter Wilson<sup>†</sup>

Catholic University of America

Now at [peter.r.wilson@boeing.com](mailto:peter.r.wilson@boeing.com)

2003/09/26

## Abstract

The **tocloft** package provides means of controlling the typographic design of the Table of Contents, List of Figures and List of Tables. New kinds of ‘List of ...’ can be defined.

The package has been tested with the **tocbibind**, **minitoc**, **ccaption**, **subfigure**, **float**, **fncychap**, and **hyperref** packages.

## Contents

<b>1</b>	<b>Introduction</b>	<b>2</b>
1.1	<b>L</b> A <b>T</b> E <b>X</b> ’s methods . . . . .	2
<b>2</b>	<b>The <b>tocloft</b> package</b>	<b>6</b>
2.1	Package options . . . . .	7
2.2	Changing the titles . . . . .	7
2.3	Typesetting the entries . . . . .	8
2.4	New list of... . . . . .	12
2.5	Experimental utilities . . . . .	15
2.6	Usage with other packages . . . . .	17
<b>3</b>	<b>The package code</b>	<b>18</b>
3.1	Support for the <b>subfigure</b> package . . . . .	38
3.2	New list of... . . . . .	40
3.3	Switching page numbering . . . . .	45
3.4	Experimental utilities . . . . .	48

## List of Figures

1	Layout of a ToC (LoF, LoT) entry . . . . .	3
---	--	---

---

<sup>\*</sup>This file (**tocloft.dtx**) has version number v2.3c, last revised 2003/09/26.

<sup>†</sup>After May 2004 at: [pandwilson at earthlink dot net](mailto:pandwilson@earthlink.net)

## List of Tables

## 1 Indents and Numwidths . . . . . 4

## 1 Introduction

In the standard classes the typographic design of the Table of Contents (ToC), the List of Figures (LoF) and List of Tables (LoT) is fixed or, more precisely, it is buried within the class definitions. The `tocloft` package provides handles for an author to change the design to meet the needs of the particular document.

Elements of the package were developed as part of a class and package bundle for typesetting ISO standards [Wil96b]. This manual is typeset according to the conventions of the L<sup>A</sup>T<sub>E</sub>X DOCSTRIP utility which enables the automatic extraction of the L<sup>A</sup>T<sub>E</sub>X macro source files [GMS94].

Section 2 describes the usage of the package. Commented source code for the package is in Section 3.

The package has been tested in combination with at least the `tocbibind` package [Wil00], the `minitoc` package [Dru99], the `ccaption` package [Wil01], the `subfigure` package [Coc95] (versions 2.0 and 2.1), the `algorithm` package [Wil96a] (which, in turn, calls the `float` package [Lin95]) and the `fncychap` package [Lin97]. It also works with the `hyperref` package. Please send me any comments as to how you think that the package can be improved, or of any interesting examples of how you have used it.<sup>1</sup>

## 1.1 L<sup>A</sup>T<sub>E</sub>X's methods

This is a general description of how L<sup>A</sup>T<sub>E</sub>X does the processing for a Table of Contents. As the processing for List of Figures and List of Tables is similar I will, without loss of generality, just discuss the ToC.

`\addcontentsline` L<sup>A</sup>T<sub>E</sub>X generates a `.toc` file if the document contains a `\tableofcontents` command. The sectioning commands<sup>2</sup> put entries into the `.toc` file by calling the L<sup>A</sup>T<sub>E</sub>X `\addcontentsline{<file>}{<kind>}{<title>}` command, where `<file>` is the file extension (e.g., `toc`), `<kind>` is the kind of entry (e.g., `section` or `subsection`), and `<title>` is the (numbered) title text. In the cases where there is a number, the `<title>` argument is given in the form `\numberline{number} title-text`.

NOTE: The `hyperref` package dislikes authors using `\addcontentsline`. To get it to work properly with `hyperref` you normally have to put `\phantomsection` (a macro defined within the `hyperref` package) immediately before `\addcontentsline`.

The `\addcontentsline` command writes an entry to the given file in the form `\contentsline{<kind>}{<title>}{<page>}` where `<page>` is the page number. For each `<kind>`, L<sup>A</sup>T<sub>E</sub>X provides a command `\l@kind{<title>}{<page>}` which performs the actual typesetting of the `\contentsline` entry.

The general layout of a typeset entry is illustrated in Figure 1. There are three

<sup>1</sup>Thanks to Rowland ([rebecca@astrid.u-net.com](mailto:rebecca@astrid.u-net.com)), John Foster ([john@isjf.demon.co.uk](mailto:john@isjf.demon.co.uk)), Kasper ([kgb@dkik.dk](mailto:kgb@dkik.dk)), Lee Nave ([nave@math.washington.edu](mailto:nave@math.washington.edu)), and Andrew Thurber




Figure 1: Layout of a ToC (LoF, LoT) entry

internal L<sup>A</sup>T<sub>E</sub>X commands that are used in the typesetting. The page number is typeset flushright in a box of width  $\text{\@pnumwidth}$ , and the box is at the righthand margin. If the page number is too long to fit into the box it will stick out into the righthand margin. The title text is indented from the righthand margin by an amount given by  $\text{\@tocrmarg}$ . Note that  $\text{\@tocrmarg}$  should be greater than  $\text{\@pnumwidth}$ . Some entries are typeset with a dotted leader between the end of the title text and the righthand margin indentation. The distance, in *math units*<sup>3</sup> between the dots in the leader is given by the value of  $\text{\@dotsep}$ . In the standard classes the same values are used for the ToC, LoF and the LoT.

The standard values for these internal commands are:

- $\text{\@pnumwidth} = 1.55\text{em}$
- $\text{\@tocrmarg} = 2.55\text{em}$
- $\text{\@dotsep} = 4.5$

The values can be changed by using `\renewcommand`, in spite of the fact that the first two appear to be lengths.

Dotted leaders are not available for Part and Chapter ToC entries (nor for Section entries in the `article` class and its derivatives).

`\numberline`

Each `\l@kind` macro is responsible for setting the general *indent* from the lefthand margin, and the *numwidth*. The `\numberline{\langle number\rangle}` macro is responsible for typesetting the number flushleft in a box of width *numwidth*. If the number is too long for the box then it will protrude into the title text. The title text is indented by (*indent* + *numwidth*) from the lefthand margin. That is, the title text is typeset in a block of width ( $\text{\linewidth} - \text{\@pnumwidth} - \text{\@dotsep}$ ).

---

([athurber@emba.uvm.edu](mailto:athurber@emba.uvm.edu)) for their suggestions.

<sup>2</sup>For figures and tables it is the `\caption` command that populates the `.lof` and `.lot` files.

<sup>3</sup>There are 18mu to 1em.

Table 1: Indents and Numwidths (in ems)

Entry	Level	Chaptered		Otherwise	
		indent	numwidth	indent	numwidth
part	-1	0	—	0	—
chapter	0	0	1.5		
section	1	1.5	2.3	0	1.5
subsection	2	3.8	3.2	1.5	2.3
subsubsection	3	7.0	4.1	3.8	3.2
paragraph	4	10.0	5.0	7.0	4.1
subparagraph	5	12.0	6.0	10.0	5.0
figure/table	(1)	1.5	2.3	1.5	2.3

Table 1 lists the standard values for the *indent* and *numwidth*. There is no explicit *numwidth* for a part; instead a gap of 1em is put between the number and the title text. Note that for a sectioning command the values depend on whether or not the document class provides the \chapter command. Also, which somewhat surprises me, the table and figure entries are all indented.

**\@dottedtocline** Most of the \l@kind commands are defined in terms of the \@dottedtocline command. This command takes three arguments:

\@dottedtocline{\seclevel}{\indent}{\numwidth}.

For example, one definition of the \l@section command is:

\newcommand\*{\l@section}{\@dottedtocline{1}{1.5em}{2.3em}}

If it is necessary to change the default typesetting of the entries, then it is usually necessary to change these definitions (but the tocloft package gives you handles to easily alter things without having to know the L<sup>A</sup>T<sub>E</sub>X internals).

You can use the \addcontentsline command to add \contentsline commands to a file.

**\addtocontents** L<sup>A</sup>T<sub>E</sub>X also provides the \addtocontents{\file}{\text} command that will insert *text* into *file*. You can use this for adding extra text and/or macros into the file, for processing when the file is typeset by \tableofcontents (or whatever other command is used for *file* processing, such as \listoftables for a .lot file).

As \addcontentsline and \addtocontents write their arguments to a file, any fragile commands used in their arguments must be \protected.

You can make certain adjustments to the ToC etc., layout without using any package. Some examples are:

- If your page numbers stick out into the righthand margin

```
\renewcommand{\pnumwidth}{3em} \renewcommand{\@tocrmarg}{4em}
```

but using lengths appropriate to your document.

- To have the (sectional) titles in the ToC, etc., typeset ragged right with no hyphenation

```
\renewcommand{\@tocrmarg}{2.55em plus1fil}
```

where the value `2.55em` can be changed for whatever margin space you want.

- The dots in the leaders can be eliminated by increasing `\@dotsep` to a large value:

```
\renewcommand{\@dotsep}{10000}
```

- To have dotted leaders in your ToC and LoF but not in your LoT:

```
...
\tableofcontents
\makeatletter \renewcommand{\@dotsep}{10000} \makeatother
\listoftables
\makeatletter \renewcommand{\@dotsep}{4.5} \makeatother
\listoffigures
...
```

For this document I used this method to double the dot spacing for the LoF with respect to that for the ToC. As you can see, it is much better that all dot leaders have the same spacing.

- To add a horizontal line across the whole width of the ToC below an entry for a Part:

```
\part{Part title}
\addtocontents{toc}{\protect\mbox{}\protect\hrulefill\par}
```

Note that as both `\addtocontents` and `\addcontentsline` write their arguments to a file, it means that any *fragile* commands in their arguments must be protected by preceding each fragile command with `\protect`. The result of the example above would be the following two lines in the `.toc` file (assuming that it is the second Part and is on page 34):

```
\contentsline {part}{II\hspace {1em}Part title}{34}
\mbox {} \hrulefill \par
```

If the `\protect`s were not used, then the second line would instead be:

```
\unhbox \voidb@x \hbox {} \unhbox \voidb@x \leaders \hrule \hfill \kern \z@ \par
```

- You may get undesired page breaks in the ToC. For example you may have a long multiline section title and in the ToC there is a page break between the lines. After your document is stable you can use `\addtocontents` at appropriate places in the body of the document to adjust the page breaking in the ToC. As examples:
  - `\addtocontents{toc}{\protect\newpage}` to force a page break.
  - `\addtocontents{toc}{\protect\enlargethispage{2\baselineskip}}` to make the page longer.
  - `\addtocontents{toc}{\protect\needspace{2\baselineskip}}` to specify that if there is not a vertical space of two baselines left on the page then start a new page (the `\needspace` macro is defined in the `needspace` package).

Remember, if you are modifying any command that includes an `@` sign then this must be done in either a `.sty` file or if in the document itself it must be surrounded by `\makeatletter` and `\makeatother`. For example, if you want to modify `\@dotsep` in the preamble to your document you have to do it like this:

```
\makeatletter
\renewcommand{\@dotsep}{9.0}
\makeatother
```

## 2 The `tocloft` package

The `tocloft` package provides means of specifying the typography of the Table of Contents (ToC), the List of Figures (LoF) and the List of Tables (LoT).

```
\tableofcontents
\listoffigures
\listoftables
```

The ToC, LoF, and LoT are printed at the point in the document where these commands are called, as per normal L<sup>A</sup>T<sub>E</sub>X. However, there is one difference between the standard L<sup>A</sup>T<sub>E</sub>X behaviour and the behaviour with the `tocloft` package. In the standard L<sup>A</sup>T<sub>E</sub>X classes that have `\chapter` headings, the ToC, LoF and LoT each appear on a new page. With the `tocloft` package they do not necessarily start new pages; if you want them to be on new pages you may have to specifically issue an appropriate command beforehand. For example:

```
...
\clearpage
\tableofcontents
\clearpage
\listoftables
...
```

`\tocloftpagestyle`

The `\thispagestyle` page style of the ToC, LoF and/or LoT is set by the command `\tocloftpagestyle{<style>}`, where `<style>` is one of the available page styles. The package initially sets `\tocloftpagestyle{plain}`.

## 2.1 Package options

The package takes the following options:

`subfigure` This option is required if, and only if, the `tocloft` and `subfigure` packages are being used together. The two packages can be specified in any order.

`titles` The `titles` option causes the titles of the ToC, LoF, and LoT lists to be typeset using the default L<sup>A</sup>T<sub>E</sub>X methods. This can be useful, for example, when the `tocloft` and `fncychap` packages are used together and the ‘fancy’ chapter styles should be used for the ToC, etc., titles.

If you use the `titles` option you can ignore the next section and continue reading at section 2.3.

## 2.2 Changing the titles

Commands are provided for controlling the appearance of the titles. Following L<sup>A</sup>T<sub>E</sub>X custom, the title texts are the values of the `\contentsname`, `\listfigurename` and `\listtablename` commands.

Similar sets of commands are provided for ToC, LoF and LoT title typesetting control. For convenience (certainly mine, and hopefully yours) in the following descriptions I will use Z to stand for ‘toc’ or ‘lof’ or ‘lot’. For example, `\cftmarkZ` stands for `\cftmarktoc` or `\cftmarklof` or `\cftmarklot`.

These macros set the appearance of the running heads on the ToC, LoF, and LoT pages. You probably don’t need to change these.

These lengths control the vertical spacing before and after the titles. You can change them from their default values by using `\setlength`.

The code used for typesetting the ToC title looks like

```
{\cfttoctitlefont {\contentsname}{\cftaftertoctitle}}\par
```

By default, `\cftZtitlefont` is defined as a font specification (e.g., `\Large\bfseries`), and `\cftafterZtitle` is empty. These commands can be changed (via `\renewcommand`) to change the typesetting. As examples:

- `\renewcommand{\cftZtitlefont}{\hfill\Large\itshape}` will result in a Large italic title typeset flushright.
- `\renewcommand{\cftZtitlefont}{\hfill\Large\bfseries}` together with `\renewcommand{\cftafterZtitle}{\hfill}` will give a centered Large bold title.
- Doing

```
\renewcommand{\cftafterZtitle}{%
 \\[\baselineskip]\mbox{}\\hfill{\normalfont Page}}
```

will put the word ‘Page’ flushright on the line following the title. (If you do this, then you may need to decrease `\cftafterZtitleskip`).

- `\renewcommand{\cftafterZtitle}{\thispagestyle{empty}}` will make the page with the title empty (i.e., the page number will not be printed).

### 2.3 Typesetting the entries

Commands are also provided to enable finer control over the typesetting of the different kinds of entries. The parameters defining the default layout of the entries are illustrated as part of the `layouts` package or in [GMS94, page 34], and are repeated in Figure 1.

`\cftdot`

In the default ToC typesetting only the more minor entries have dotted leader lines between the sectioning title and the page number. The `tocloft` package provides for general leaders for all entries. The ‘dot’ in a leader is given by the value of `\cftdot`. Its default definition is `\newcommand{\cftdot}{.}` which gives the default dotted leader. By changing `\cftdot` you can use symbols other than a period in the leader. For example

```
\renewcommand{\cftdot}{\ensuremath{\ast}}
```

will result in a dotted leader using asterisks as the symbol.

`\cftdotsep`  
`\cftnodots`

Each kind of entry can control the separation between the dots in its leader (see below). For consistency though, all dotted leaders should use the same spacing. The macro `\cftdotsep` specifies the default spacing. Its value is a number. However, if the separation is too large then no dots will be actually typeset. The macro `\cftnodots` is a separation value that is ‘too large’.

`\cftsetpnumwidth`  
`\cftsetrmarg`

The page numbers are typeset in a fixed width box. The command `\cftsetpnumwidth{<length>}` can be used to change the width of the box (L<sup>A</sup>T<sub>E</sub>X’s internal `\@pnumwidth`). The title texts will end before reaching the righthand margin. `\cftsetrmarg{<length>}` can be used to set this distance (L<sup>A</sup>T<sub>E</sub>X’s internal `\@tocrmarg`). Note that the length used in `\cftsetrmarg` should be greater than the length set in `\cftsetpnumwidth`. These values should remain constant in any given document.

`\cftparskip`

Normally the `\parskip` in the ToC, etc., is zero. This may be changed by changing the `\cftparskip` length. Note that the current value of `\cftparskip` is used for the ToC, LoF and LoT, but you can change the value before calling `\tableofcontents` or `\listoffigures` or `\listoftables` if one or other of these should have different values (which is not a good idea).

In the following I will use X to stand for the following:

- `part` for `\part` titles
- `chap` for `\chapter` titles
- `sec` for `\section` titles
- `subsec` for `\subsection` titles

- `subsubsec` for `\subsubsection` titles
- `para` for `\paragraph` titles
- `subpara` for `\ subparagraph` titles
- `fig` for figure `\caption` titles
- `subfig` for subfigure `\caption` titles
- `tab` for table `\caption` titles
- `subtab` for subtable `\caption` titles

`\cftbeforeXskip` This controls the vertical space before an entry. It can be changed by using `\setlength`.

`\cftXindent` This controls the indentation of an entry from the left margin (*indent* in Figure 1). It can be changed using `\setlength`.

`\cftXnumwidth` This controls the space allowed for typesetting title numbers (*numwidth* in Figure 1). It can be changed using `\setlength`. Second and subsequent lines of a multiline title will be indented by this amount.

The remaining commands are related to the specifics of typesetting an entry. This is a simplified pseudo-code version for the typesetting of numbered and unnumbered entries.

```
{\cftXfont {\cftXpresnum SNUM\cftXaftersnum\hfil} \cftXaftersnumb TITLE}%
{\cftXleader}{\cftXpagefont PAGE}\cftXafterpnum\par

{\cftXfont TITLE}{\cftXleader}{\cftXpagefont PAGE}\cftXafterpnum\par
```

where `SNUM` is the section number, `TITLE` is the title text and `PAGE` is the page number. In the numbered entry the pseudo-code

```
{\cftXpresnum SNUM\cftaftersnum\hfil}
```

is typeset within a box of width `\cftXnumwidth`.

`\cftXfont` This controls the appearance of the title (and its preceding number, if any). It may be changed using `\renewcommand`.

`\cftXpresnum` Normally the section number is typeset within a box of width `\cftXnumwidth`.  
`\cftXaftersnum` Within the box the macro `\cftXpresnum` is first called, then the number is typeset, and next the `\cftXaftersnum` macro is called after the number is typeset. The last command within the box is `\hfil` to make the box contents flushleft. After the box is typeset the `\cftXaftersnumb` macro is called before typesetting the title text. All three of these can be changed by `\renewcommand`. By default they are defined to do nothing.

In the standard classes the ToC entry for a `\part` is just typeset as the number and title, followed by the page number, with the `\cftpaptpresnum` macro being called before typesetting the number and title. When a standard class is used the `\cftpaptaftersnum` and `\cftpaptaftersnumb` macros have no effect, but they may do something if a non-standard class is used.

```
\cftXleader  
\cftXdotsep
```

`\cftXleader` defines the leader between the title and the page number; it can be changed by `\renewcommand`. The spacing between any dots in the leader is controlled by `\cftXdotsep` (`\@dotsep` in Figure 1). It can be changed by `\renewcommand` and its value must be either a number (e.g., 6.6 or `\cftdotsep`) or `\cftnodots` (to disable the dots). The spacing is in terms of *math units* where there are 18mu to 1em.

```
\cftXpagefont
```

This defines the font to be used for typesetting the page number. It can be changed by `\renewcommand`.

```
\cftXafterpnum
```

This macro is called after the page number has been typeset. Its default is to do nothing. It can be changed by `\renewcommand`.

```
\cftsetindents
```

The command `\cftsetindents{<entry>}{<indent>}{{<numwidth>}}` sets the `<entry>`'s *indent* to the length `<indent>` and its *numwidth* to the length `<numwidth>`. The `<entry>` argument is the name of one of the standard entries (e.g., `subsection`) or the name of entry that has been defined with the `tocloft` package. For example `\cftsetindents{figure}{0em}{1.5em}` will make figure entries left justified.

Various effects can be achieved by changing the definitions of `\cftXfont`, `\cftXaftersnum`, `\cftXaftersnumb`, `\cftXleader` and `\cftXafterpnum`, either singly or in combination. For the sake of some examples, assume that we have the following initial definitions

```
\newcommand{\cftXfont}{}  
\newcommand{\cftXaftersnum}{}  
\newcommand{\cftXaftersnumb}{}  
\newcommand{\cftXleader}{\cftdotfill{\cftXdotsep}}  
\newcommand{\cftXdotsep}{\cftdotsep}  
\newcommand{\cftXpagefont}{}  
\newcommand{\cftXafterpnum}{}  
%
```

(Note that the same font should be used for the title, leader and page number to provide a coherent appearance).

- To eliminate the dots in the leader:

```
\renewcommand{\cftXdotsep}{\cftnodots}
```

- To put something (e.g., a name) before the title (number):

```
\renewcommand{\cftXpresnum}{SOMETHING }
```

- To add a colon after the section number:

```
\renewcommand{\cftXaftersnum}{:}
```

- To put something before the title number, add a colon after the the title number, set everything in bold font, and start the title text on the following line:

```
\renewcommand{\cftXfont}{\bfseries}
\renewcommand{\cftXleader}{\bfseries\cftdotfill{\cftXdotsep}}
\renewcommand{\cftXpagefont}{\bfseries}
\renewcommand{\cftXpresnum}{SOMETHING }
\renewcommand{\cftXaftersnum}{:}
\renewcommand{\cftXaftersnumb}{\\"}
```

If you are adding text in the number box in addition to the number, then you will probably have to increase the width of the box so that multiline titles have a neat vertical alignment; changing box widths usually implies that the indents will require modification as well.<sup>4</sup> One possible method of adjusting the box width for the above example is:

```
\newlength{\mylen} % a "scratch" length
\settowidth{\mylen}{\bfseries\cftXpresnum\cftXaftersnum} % extra space
\addtolength{\cftXnumwidth}{\mylen} % add the extra space
```

- To set the section numbers flushright:<sup>5</sup>

```
\setlength{\mylen}{0.5em} % need some extra space at end of number
\renewcommand{\cftXpresnum}{\hfill} % note the double 'l'
\renewcommand{\cftXaftersnum}{\hspace*{\mylen}}
\addtolength{\cftXnumwidth}{\mylen}
```

In the above, the added initial \hfill in the box overrides the final \hfil in the box, thus shifting everything to the right hand end of the box. The extra space is so that the number is not typeset immediately at the left of the title text.

- To set the entry ragged left (but this only looks good for single line titles):

```
\renewcommand{\cftXfont}{\hfill\bfseries}
\renewcommand{\cftXleader}{}
```

- To set the page number immediately after the entry text instead of at the righthand margin:

```
\renewcommand{\cftXleader}{}
\renewcommand{\cftXafterpnum}{\cftparskip}
```

---

<sup>4</sup>Lyndon Dudding ([lyndon.dudding@totalise.co.uk](mailto:lyndon.dudding@totalise.co.uk)) discovered this.

<sup>5</sup>With thanks to David Holz ([1bda@earthlink.net](mailto:1bda@earthlink.net)) for requesting this.

By default the `\parfillskip` value is locally set to fill up the last line of a paragraph. Just changing `\cftXleader` puts horrible interword spaces into the last line of the title. The `\cftparskip` command is part of the `tocloft` package and is provided just so that the above effect can be achieved.

`\cftpagenumbersoff  
\cftpagenumberson`

The command `\cftpagenumbersoff{<entry>}` will eliminate the page numbers for `<entry>` in the listing, where `<entry>` is the name of one of the standard kinds of entries (e.g., `subsection`, or `figure` — including `subfigure` if the `subfigure` package is used — etc.), or the name of a new entry defined with the `tocloft` package.

The command `\cftpagenumberson{<entry>}` reverses the effect of a corresponding `\cftpagenumbersoff`.

One question that appeared on the `comp.text.tex` newsgroup asked how to get the titles of Appendices list in the ToC *without* page numbers. Here is a simple way of doing it, assuming the document has chapters

```
...  
\appendix  
\addtocontents{toc}{\cftpagenumbersoff{chapter}}  
\chapter{First appendix}
```

If there are other chaptered headings to go into the ToC after the appendices, then it will be necessary to do a similar

```
\addtocontents{toc}{\cftpagenumberson{chapter}}
```

to restore the page numbering in the ToC.

Similarly, if you are using the `subfigure` package you may want to eliminate the page numbers for the `subfigure` captions. This can be accomplished by:

`\cftpagenumbersoff{subfigure}`

At this point, I leave it up to your ingenuity as to other effects that you can achieve. However, if you come up with further examples, let me know for possible inclusion in a later version of this document.

## 2.4 New list of...

`\newlistof`

The command `\newlistof[<within>]{<entry>}{<ext>}{<listofname>}` creates a new List of ..., and assorted commands to go along with it.

The first required argument, `<entry>` is used to define a new counter called `entry`. The optional `<within>` argument can be used so that `entry` gets reset to one every time the counter called `within` is changed. That is, the first two arguments are equivalent to calling `\newcounter{<entry>}[<within>]`.

The next argument, `<ext>`, is the file extension for the new List of. The last argument, `<listofname>`, is the text for the heading of the new List of. As an example:

```
\newcommand{\listanswername}{List of Answers}  
\newlistof[chapter]{answer}{ans}{\listanswername}
```

will create a new `answer` counter that will be reset at the start of each `\chapter{...}`. Any answer titles will be written to the file `jobname.ans` and `\listanswernname` will be used as the list heading. A command `\listofanswer` is created which can be used just like the `\listoftables` or `tableofcontents` commands to generate a listing. It is up to you to specify how the entries are put into the new List of Answers. Here is a very simple example, remembering that an `answer` counter has been created.

```
\newcommand{\answer}[1]{%
  \refstepcounter{answer}
  \par\noindent\textbf{Answer} \theanswer. #1
  \addcontentsline{ans}{answer}{\protect\numberline{\theanswer}\#1}\par}
```

which, when used like:

`\answer{Hard}` The `\ldots` will print as:

#### Answer 1. Hard

The ...

As mentioned above, the `\newlistof` command creates several new commands, most of which you should now be familiar with. For convenience, assume that `\newlistof{X}{Z}{...}` has been issued; so `X` is the name of the new counter and corresponds to the `X` in section 2.3, and `Z` is the new file extension and corresponds to the `Z` in section 2.2. Then, among others, the following new commands will be made available.

The five commands, `\cftmarkZ`, `\cftbeforeZtitleskip`, `\cftafterZtitleskip`, `\cftZtitlefont`, and `\cftafterZtitle`, are analogous to the commands of the same names described in section 2.2.

The command `\listofX` is similar to `\listoftables`, etc., in that it typesets the new listing at the point where it is called.

The command `\Zdepth{<number>}` is analogous to the standard `\tocdepth{<number>}` command, in that it specifies that entries in the new listing should not be typeset if their numbering level is greater than `<number>`. The default definition is `\setcounter{Zdepth}{1}`.

The command `\newlistentry[<within>]{<entry>}{<ext>}{<level-1>}` creates new commands for typesetting a new kind of entry in a listing. It is used internally by the `\newlistof` command but may be used independently.

The first required argument, `<entry>` is used to define a new counter called `entry`. The optional `<within>` argument can be used so that `entry` gets reset to one every time the counter called `within` is changed. That is, the first two arguments are equivalent to calling `\newcounter{<entry>}[<within>]`. The second required argument, `<ext>`, is the file extension for the entry listing. The last argument, `<level-1>`, is a number specifying the numbering level minus one, of the entry in a listing. For example, the command

`\newlistof[chapter]{answer}{ans}{\listanswernname}`

will call the command:

`\newlistentry[chapter]{answer}{ans}{0}`

Calling `\newlistentry` creates several new commands. Assuming that it is called as `\newlistentry[within]{X}{Z}{N}`, where X and Z are similar to the previous uses of them, and N is an integer number, then the following commands are made available.

The set of commands `\cftbeforeXskip`, `\cftXfont`, `\cftXpresnum`, `\cftXaftersnum`, `\cftXaftersnumb`, `\cftXleader`, `\cftXdotsep`, `\cftXpagefont`, and `\cftXafterpnum`, are analogous to the commands of the same names described in section 2.3. Their default values are also as described earlier.

The default values of `\cftXindent` and `\cftXnumwidth` are set according to the value of the *(level-1)* argument (i.e., N in this example). For N=0 the settings correspond to those for sections in non-chaptered documents, as listed in Table 1. For N=4 the settings correspond to subparagraphs in non-chaptered documents, and for intermediate values correspond to the matching sectional division in chaptered documents. For values of N less than zero or greater than four, or for non-default values, use the `\cftsetindents` command to set the values.

`\l@X` `\l@X` is an internal command that typesets an entry in the list, and is defined in terms of the above `\cft*X*` commands. It will not typeset an entry if `\Zdepth` is N or less, where Z is the listing's file extension.

`\theX` The command `\theX` prints the value of the X counter. It is initially defined so that it prints arabic numerals. If the optional *(within)* argument is used, `\theX` is defined as

```
\renewcommand{\theX}{\thewithin.\arabic{X}} otherwise as
\renewcommand{\theX}{\arabic{X}}.
```

As an example of the independent use of `\newlistentry`, the following will set up for sub-answers.

```
\newlistentry[answer]{subanswer}{1}
\cftsetindents{subanswer}{1.5em}{3.0em}
\renewcommand{\thesubanswer}{\theanswer.\alph{subanswer}}
\newcommand{\subanswer}[1]{%
  \refstepcounter{subanswer}
  \par\textrbf{\thesubanswer} #1
  \addcontentsline{ans}{subanswer}{\protect\numberline{\thesubanswer}#1}}
\setcounter{ansdepth}{2}
```

And then:

```
\answer{Harder} The \ldots
\subanswer{Reformulate the problem} It assists \ldots
```

will be typeset as:

**Answer 2. Harder**

The ...

**2.a) Reformulate the problem** It assists ...

By default the answer entries will appear in the List of Answers listing (typeset by the `\listofanswer` command). In order to get the subanswers to appear, the `\setcounter{ansdepth}{2}` command was used above.

To turn off page numbering for the subanswers, do  
`\cftpagenumbersoff{subanswer}`

As another example of `\newlistentry`, suppose that an extra sectioning division below `subparagraph` is required, called `subsubpara`. The `\subsubpara` command itself can be defined via the LaTeX kernel `\@startsection` command. Also it is necessary to define a `\subsubparamark` macro, a new `subsubpara` counter, a `\thesubsubpara` macro and a `\l@subsubpara` macro. Using the `tocloft` package's `\newlistentry` takes care of most of these as shown below (remember the caveats about commands with @ signs in them).

```
\newcommand{\subsubpara}{\@startsection{subpara}%
{6}{}%                                level
{\parindent}{}%                         indent from left margin
{3.25ex \oplus1ex \ominus .2ex}{}%      skip above heading
{-1em}{}%                            runin heading with 1em between title & text
{\normalfont\normalsize\itshape}{}% italic number and title
}
\newlistentry[subparagraph]{subsubpara}{toc}{5}
\cftsetindents{subsubpara}{14.0em}{7.0em}
\newcommand*\subsubparamark[1]{}%      % gobble heading mark
```

Each List of... uses a file to store the list entries, and these files must remain open for writing throughout the document processing. TeX has only a limited number of files that it can keep open, and this puts a limit on the number of listings that can be used. For a document that includes a ToC but no other extra ancillary files (e.g., no index or bibliography output files) the maximum number of LoX's, including a LoF and LoT, is no more than about eleven. If you try and create too many new listings LaTeX will respond with the error message:

No room for a new write

If you get such a message the only recourse is to redesign your document.

The `tocloft` package does not provide a simple means of specifying new Lists of Floats or float environments. For those, I recommend the `ccaption` package [Wil01].

## 2.5 Experimental utilities

The macros described in this section are even more experimental than those described previously.

`\cftchapterprecis` Some old style novels, and even some modern text books,<sup>6</sup> include a short synopsis of the contents of the chapter either immediately after the chapter heading or in the Toc, or in both places.

The command `\cftchapterprecis{<text>}` prints its argument both at the point in the document where it is called, and also adds it to the `.toc` file. For example:

---

<sup>6</sup>For example, Robert Sedgewick, *Algorithms*, Addison-Wesley, 1983.

```

...
\chapter{} % first chapter
\cftchapterprecis{Our hero is introduced; family tree; early days.}
...

```

\cftchapterprecishere  
\cftchapterprecistoc

The `\cftchapterprecis` command calls these two commands to print the text in the document (the `\...here{text}` command) and to put it into the ToC (the `\...toc{text}` command). These can be used individually if required.

Sometimes it may be desirable to make a change to the global parameters for an individual entry. For example, a figure might be placed on the end paper of a book (the inside of the front or back cover), and this needs to be placed in a LoF with the page number set as, say ‘inside front cover’. If ‘inside front cover’ is typeset as an ordinary page number it will stick out into the margin. Therefore, the parameters for this particular entry need to be changed.

\cftlocalchange

The command `\cftlocalchange{file}{{pnumwidth}}{tocrmarg}` will write an entry into *file* to reset the global parameters. The command should be called again after any special entry to reset the parameters back to their usual values. Any fragile commands used in the arguments must be protected.

\cftaddtitleline

The command `\cftaddtitleline{file}{{kind}}{title}{{page}}` will write a `\contentsline` entry into *file* for a *kind* entry with title *title* and page number *page*. That is, an entry is made of the form:

`\contentsline{kind}{title}{page}`

Any fragile commands used in the arguments must be protected.

\cftaddnumtitleline

The command `\cftaddnumtitleline{file}{{kind}}{num}{{title}}{page}` is similar except that it also includes *num* as the argument to the `\numberline`. That is, an entry is made of the form:

`\contentsline{kind}{{\numberline{num}}}{title}{page}`

Any fragile commands used in the arguments must be protected.

As an example of the use of these commands, noting that the default L<sup>A</sup>T<sub>E</sub>X values for `\@pnumwidth` and `\@tocrmarg` are 1.55em and 2.55em respectively, one might do the following for a figure on the frontispiece page.

```

...
% this is the frontispiece page with no number
% draw or import the picture (with no \caption)
\cftlocalchange{lof}{4em}{5em} % make pnumwidth big enough for
                           % frontispiece and change margin to suit
\cftaddtitleline{lof}{figure}{The title}{frontispiece}
\cftlocalchange{lof}{1.55em}{2.55em} % return to normal settings
...

```

Recall that a `\caption` command will put an entry in the `.lof` file, which is not wanted here. If a caption is required, then you can either craft one yourself or, assuming that your general captions are not too exotic, use the `\legend` command from the `ccaption` package. If the illustration is numbered, use the `\cftaddnumtitleline` command instead of `\cftaddtitleline`.

## 2.6 Usage with other packages

The `tocloft` and `tocbibind` packages can be used together in the same document. The `tocbibind` package provides easy means of adding document elements like the bibliography or the index to the Table of Contents. However there are two known potential problems:

- The 1998/11/15 version of `tocbibind` may give surprising results if the `\toctocname`, `\toclotname` or `\toclofname` commands have been used. You should consider getting the current version of `tocbibind`.
- If the argument to the `\tocotherhead` command is other than one of the normal sectioning divisions (i.e., part through to sub-paragraph) such as `\tocotherhead{clause}`, then this will almost certainly cause a problem (as the `tocloft` package will not know how to define the corresponding `\l@clause` command). In such a case you will have to supply the appropriate macros yourself.

`\@cftbsnum` Some packages, like the `float` package by Anselm Lingnau, enable the creation of other kinds of *List of . . .*. The `tocloft` package is only minimally able to change the formatting of these, principally because the packages are independent of each other and, in the case of the `float` package, new kinds of float environments and their associated lists can be created on the fly at any point in a document. Some aspects of the typesetting are controlled by `\@cftbsnum`, `\@cftasnum` and `\@cftasnumb` commands. These are equivalent to the `\cftXpresnum`, `\cftXaftersnum` and `\cftXaftersnumb` commands described earlier. By default they are defined to do nothing, but may be renewed to do something.

The `tocloft` and `minitoc` packages have an unfortunate interaction,<sup>7</sup> which fortunately can be fixed. In the normal course of events, when `minitoc` is used in a chaptered document it will typeset section entries in the minitocs in bold font. If `tocloft` is used in conjunction with `minitoc`, then the minitoc section entries are typeset in the normal font, except for the page numbers which are in bold font, while the ToC section entries are all in normal font.

One cure, if you want the minitoc section entries to be all in normal font is to put:

```
\renewcommand{\mtcSfont}{\small\normalfont}
```

in the preamble.

Otherwise, the cure is the following incantation:

```
\renewcommand{\cftsecfont}{\bfseries}
\renewcommand{\cftsecleader}{\bfseries\cftdotfill{\cftdotsep}}
\renewcommand{\cftsecpagefont}{\bfseries}
```

---

<sup>7</sup>Discovered by Lyndon Dudding ([lyndon.dudding@totalise.co.uk](mailto:lyndon.dudding@totalise.co.uk)).

To have the section entries in both the ToC and the minitocs in bold then put the incantation in the preamble. To have only the minitoc section entries in bold while the ToC entries are in the normal font, put the incantation between the `\tableofcontents` command and the first `\chapter` command.

In general, use with other packages that redefine any of the macros that `tocloft` also modifies is likely to be problematic.

### 3 The package code

Announce the name and version of the package, which requires L<sup>A</sup>T<sub>E</sub>X 2 <sub>$\varepsilon$</sub>  but no extra packages.

```
1 <*usc>
2 \NeedsTeXFormat{LaTeX2e}
3 \ProvidesPackage{tocloft}[2003/09/26 v2.3c parameterised ToC, etc., typesetting]
```

`\PRWPackageNote` These two commands write a Package Note to the terminal and the log file. Use  
`\PRWPackageNoteNoLine` as: `\PRWPackageNote{<package name>}{<note text>}`. The NoLine version does not show the line number. The commands are intermediate between the kernel `\PackageWarning` and `\PackageInfo` commands. I have `\provided` the `\PRW...` commands as other packages (of mine) may also incorporate them. The code is based on `lterror.dtx`.

```
4 \providecommand{\PRWPackageNote}[2]{%
5   \GenericWarning{%
6     (#1)\@spaces\@spaces\@spaces\@spaces
7   }{%
8     Package #1 Note: #2%
9   }%
10 }
11 \providecommand{\PRWPackageNoteNoLine}[2]{%
12   \PRWPackageNote{#1}{#2}@gobble}%
13 }
```

In order to try and avoid name clashes with other packages, each internal name will include the character string `@cft`.

`\@cftquit` We will be using either chapter or section type headings for the ToC, etc., so we  
`\if@cfthaschapter` need to know which of these the document class supports.

```
14 \newcommand{\@cftquit}{}
15 \newif\if@cfthaschapter
```

`\if@cftkoma` The koma classes have different defaults than the standard classes, so we need to know if a koma class has been loaded.

```
16 \newif\if@cftkoma
17   \@cftkomafalse
18 \@ifclassloaded{scrartcl}{\@cftkomatrue}{}
19 \@ifclassloaded{scrreprt}{\@cftkomatrue}{}
20 \@ifclassloaded{scrbook}{\@cftkomatrue}{}
21
```

Issue a warning if there are no recognised sectional divisions and then skip the rest of the package code.

```
22 \@ifundefined{chapter}{%
23   \cfthaschapterfalse
24   \@ifundefined{section}{%
25     \PackageWarning{tocloft}{%
26       {I don't recognize any sectional divisions so I'll do nothing}
27       \renewcommand{\cftquit}{\endinput}
28     }{\PRWPackageNoteNoLine{tocloft}{The document has section divisions}}
29   }{\cfthaschaptertrue
30     \PRWPackageNoteNoLine{tocloft}{The document has chapter divisions}}
31 Perhaps quit now.
32 \cftquit
```

Use chapter style if `\if@cfthaschapter` is TRUE, otherwise section style.

`\if@cfttocabibind` A flag that is set TRUE iff the `tocbibind` package has been loaded. The 1998/11/15 version of `tocbibind` does not necessarily work well with `tocloft`.

```
32 \newif\if@cfttocabibind
33 \AtBeginDocument{%
34   \@ifpackageloaded{tocbibind}{\cfttocabibindtrue}{\cfttocabibindfalse}
35   \if@cfttocabibind
36     \@ifpackagelater{tocbibind}{1998/11/16}{}{%
37       \PackageWarning{tocloft}{%
38         You are using a version of the tocbibind package\MessageBreak
39         that is not compatible with tocloft.\MessageBreak
40         The results may be surprising.\MessageBreak
41         Consider installing the current version of tocbibind.}}
42   \fi
43 }
```

`\if@cftnctoc` A boolean used to implement the `titles` option. It is TRUE if the ToC, LoT, LoF titles should use the default styles.

```
44 \newif\if@cftnctoc\cftnctocfalse
45 \DeclareOption{titles}{\cftnctoctrue}
46 %% \ProcessOptions\relax
```

`\if@cftsubfigopt` A boolean used to implement the `subfigure` option.

```
47 \newif\if@cftsubfigopt\cftsubfigoptfalse
48 \DeclareOption{subfigure}{\cftsubfigopttrue}
```

Process the options.

```
49
50 \ProcessOptions\relax
51
```

`\tocloftpagestyle` A user-level macro to set the pagestyle for the first page of the ToC, etc. The `\cftpagestyle` default is the `plain` pagestyle.

```

52 \newcommand{\tocloftpagestyle}[1]{%
53   \def\@cftpagestyle{\thispagestyle{#1}}}
54 \tocloftpagestyle{plain}
55

\cftmarktoc These three macros set the style for running heads. They are initialised to give
\cftmarklof the default appearance.
\cftmarklot 56 \newcommand{\cftmarktoc}{%
57   \mkboth{\MakeUppercase\contentsname}{\MakeUppercase\contentsname}}
58 \newcommand{\cftmarklof}{%
59   \mkboth{\MakeUppercase\listfigurename}{\MakeUppercase\listfigurename}}
60 \newcommand{\cftmarklot}{%
61   \mkboth{\MakeUppercase\listtablename}{\MakeUppercase\listtablename}}
62 \if@cftkoma
63   \renewcommand{\cftmarktoc}{%
64     \mkboth{\contentsname}{\contentsname}}
65   \renewcommand{\cftmarklof}{%
66     \mkboth{\listfigurename}{\listfigurename}}
67   \renewcommand{\cftmarklot}{%
68     \mkboth{\listtablename}{\listtablename}}
69 \fi

\@cfttocstart Two macros to perform the actions at the beginning and end of the \tableofcontents
\@cfttocfinish command (and friends). \@cfttocstart deals with chaptered documents, ensuring
that the ToC is typeset in a single column (see classes.dtx for the original
code). These macros are also provided by the ccaption package.
70 \providecommand{\@cfttocstart}{%
71   \if@cfthaschapter
72     \if@twocolumn
73       \restonecoltrue\onecolumn
74     \else
75       \restonecolfalse
76     \fi
77   \fi}
78 \@cfttocfinish resets, if required, twocolumn typesetting.
79 \providecommand{\@cfttocfinish}{%
80   \if@cfthaschapter
81     \if@restonecol\twocolumn\fi
82   \fi}

\phantomsection This is provided because the hyperref package screws with \addcontentsline.
83 \providecommand{\phantomsection}{}}

\@cftdobibtoc If the tocbibind package has been used and it has redefined \tableofcontents we
need to cater for that. The contents of the definition are defined in tocbibind.
84 \newcommand{\@cftdobibtoc}{%
85   \if@dototoc

```

```

86      \if@bibchapter
87          \phantomsection
88          \addcontentsline{toc}{chapter}{\contentsname}
89      \else
90          \phantomsection
91          \addcontentsline{toc}{\@tocextra}{\contentsname}
92      \fi
93  \fi}
94

\cftparskip The \parskip local to the ToC, etc., is set to the length \cftparskip.
95 \newlength{\cftparskip}
96 \setlength{\cftparskip}{0pt}
97

\tableofcontents This is a parameterised version of the default \tableofcontents command. Each class has its own definition, but we have to cater for all classes in one definition, hence some of the checks. The definition is modified after all packages have been loaded.
If the titles option has been used, then the command is not modified.
98 \AtBeginDocument{%
99 \if@cftnctoc\else
100   \renewcommand{\tableofcontents}{%
101     \cfttocstart
102     \par
103     \begingroup
104       \parindent\z@\cftparskip\cftparskip
105       \cftmaketoctitle
106     \if@cfttocbibind
107       \cftdobibtoc
108     \fi
109     \cftstarttoc{toc}%
110     \endgroup
111     \cfttocfinish
112 \fi
113 }

If tocbibind has been used, then add the ToC name to the ToC.
114 \newcommand{\cftmaketoctitle}{%
115   \addpenalty\@secpenalty
116   \if@cfthaschapter
117     \vspace*{\cftbeforetoctitleskip}
118   \else

```

\cftmaketoctitle This command typesets the title for the ToC.

```

114 \newcommand{\cftmaketoctitle}{%
115   \addpenalty\@secpenalty
116   \if@cfthaschapter
117     \vspace*{\cftbeforetoctitleskip}
118   \else

```

```

119      \vspace{\cftbeforetoctitleskip}
120  \fi
121  \@cftpagestyle
122  {\interlinepenalty@M
123  {\cfttoctitlefont\contentsname}{\cftaftertoctitle}
124  \cftmarktoc
125  \par\nobreak
126  \vskip \cftaftertoctitleskip
127  \@afterheading}

\cftbeforetoctitleskip These two lengths control the vertical spacing before and after the ToC title.
\cftaftertoctitleskip 128 \newlength{\cftbeforetoctitleskip}
129 \newlength{\cftaftertoctitleskip}

Their values depend on whether the document has chapters or not. In chaptered documents the default ToC title is typeset as a \chapter*, otherwise as a \section*.

130 \if@cfthaschapter
131   \setlength{\cftbeforetoctitleskip}{50pt}
132   \setlength{\cftaftertoctitleskip}{40pt}
133 \else
134   \setlength{\cftbeforetoctitleskip}{3.5ex \@plus 1ex \@minus .2ex}
135   \setlength{\cftaftertoctitleskip}{2.3ex \@plus .2ex}
136 \fi

\cfttoctitlefont The ToC title is typeset in the style given by \cfttoctitlefont. The macro
\cftaftertoctitle \cftaftertoctitle is called after typesetting the title. This is initialised to do
nothing. Both these macros can be redefined to do other things (e.g., adding an
\hfill to \cfttoctitlefont will make the title flushright).

137 \if@cfthaschapter
138   \newcommand{\cfttoctitlefont}{\normalfont\Huge\bfseries}
139   \if@cftkoma\renewcommand{\cfttoctitlefont}{\size@chapter\sectfont}\fi
140 \else
141   \newcommand{\cfttoctitlefont}{\normalfont\Large\bfseries}
142   \if@cftkoma\renewcommand{\cfttoctitlefont}{\size@section\sectfont}\fi
143 \fi
144 \newcommand{\cftaftertoctitle}{}}

\cftsetpnumwidth Users commands for setting \cftsetpnumwidth and \cftsetrmarg.
\cftsetrmarg 145 \newcommand{\cftsetpnumwidth}[1]{\renewcommand{\cftsetpnumwidth}{#1}}
146 \newcommand{\cftsetrmarg}[1]{\renewcommand{\cftsetrmarg}{#1}}

\cftdot In the default ToC, a dotted line can be used to provide a leader between a title and
\cftdotfill the page number. The definition of this leader is buried in the \cftdottedocline
command. The \cftdotfill{\sep} command provides a parameterised version
of the leader code, where sep is the separation between the dots in mu units.
The symbol used for the ‘dots’ in the leader is given by the value of \cftdot.
These macros are also provided by the ccaption package.

147 \providecommand{\cftdot}{.}

```

```

148 \providecommand{\cftdotfill}[1]{%
149   \leaders\hbox{$\mathfrak{m}@th\mkern #1 \mu\hbox{\cftdot}\mkern #1 \mu$}\hfill}
\cftdotsep \cftdotsep holds the default dot seperation, and is also provided by the ccaption
\cftnodots package. If the kerns in \cftdotfill are large enough, then no dots will be
printed. \cftnodots should be ‘large enough’.
150 \providecommand{\cftdotsep}{4.5}
151 \newcommand{\cftnodots}{10000}

```

Now for the trickier bits regarding the typesetting of the ToC entries.

A .toc (also .lof and .lot) file consists of a list of \contentsline{\kind}{\title}{\page} commands, where *kind* is the kind of heading (e.g., part or section or figure), *title* is the title text (including the number), and *page* is the page number. The entries are inserted into the file by calling the \addcontentsline{\file}{\kind}{\title} command, where *file* is the file extension (e.g., toc, lot) and the other arguments are the same as for the \contentsline command. (Arbitrary stuff may also be put into the file via the \addtocontents{\file}{\text} command). The typesetting of the \contentsline entries is performed by commands of the form \l@kind. The sectioning and captioning commands call \addcontentsline to insert their titles into the .toc etc., files.

For the purposes at hand it is generally impossible to treat the typesetting of a title and its number seperately, as both are bundled into the *title* argument within \contentsline. They could be handled seperately if the \contentsline command was suitably modified. If this was done, then the \addtocontentsline command would also need to be changed which would then require the sectioning and captioning commands to be modified as well. This is certainly possible, but would cause problems if any other package also modified the sectioning or captioning commands, and there are several packages which do this.

Having said this, for all but Part entries, the sectional number is typeset via the \numberline command. We can take advantage of this fact.

I have taken the decision to not touch the \contentsline macro and instead to do what can be done with it as it exists. That is, I will modify the \l@kind commands. Essentially, my new definitions consist of inlined versions of the code for \dottedtocline.

\cftparskip \numberline	The \l@kind commands modify (locally) the value of \parskip. \cftparskip is a copy of the default <i>TEXbook</i> \parskip definition. 152 \newcommand{\cftparskip}{\parskip=0pt plus1fil}  The purpose of the \numberline{\secnum} command is to typeset <i>secnum</i> left justified in a box of width \tempdima. I redefine it to add three additional parameters, namely \cftbsnum, \cftasnum and \cftasnumb (see ltsect.dtx for the original definition).
----------------------------	--

```

153 \renewcommand{\numberline}[1]{%
154   \hbox{\hbox{\cftbsnum \#1 \cftasnum \hfil}\cftasnumb}

```

\@cftbsnum Originally these were not defined but were \let to appropriate commands in the \@cftasnum \l@... commands, but they have to be defined in case something unexpected calls \@cftasnumb, for example through use of the float package.<sup>8</sup>

```
155 \newcommand{\@cftbsnum}{}
156 \newcommand{\@cftasnum}{}
157 \newcommand{\@cftasnumb}{}
```

\l@part \l@part{\langle title\rangle}{\langle page\rangle} typesets the ToC entry for a part heading. It is a parameterised copy of the default \l@part (see *classes.dtx* for the original definition and the code below for \l@subsection for an explanation of most of this code). By default, Parts (and Chapters) do not have dotted leaders. This package provides for all entries to have dotted leaders.

```
158 \newif\if@cftdopart
159 \newif\if@cfthaspart
160 \ifundefined{part}{\@cfthaspartfalse}{\@cfthasparttrue}
161 \if@cfthaspart
162 \renewcommand*{\l@part}[2]{%
163   \cftdopartfalse
164   \ifnum \c@tocdepth > -2 \relax
165     \if@cfthaschapter
166       \cftdoparttrue
167     \fi
168     \ifnum \c@tocdepth > \m@ne
169       \if@cfthaschapter \else
170         \cftdoparttrue
171       \fi
172     \fi
173   \fi
174 \if@cftdopart
175   \if@cfthaschapter
176     \addpenalty{-\@highpenalty}%
177   \else
178     \addpenalty\@secpenalty
179   \fi
180 \addvspace{\cftbeforepartskip}%
181 \begingroup
182   {\leftskip \cftpindent\relax
183    \rightskip \cftmarg
184    \parfillskip -\rightskip
185    \parindent \cftpindent\relax\cfterindenttrue
186    \interlinepenalty\@M
187    \leavevmode
188    \cftpartnumwidth\relax
189    \let\@cftbsnum \cftpresnum
190    \let\@cftasnum \cftaftersnum
191    \let\@cftasnumb \cftaftersnumb}
```

---

<sup>8</sup>This bug was discovered by Andrew Thurber when using the *tocloft* and *algorithm* packages together.

```

192      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
193      {\cftpfont \cftpartpresnum #1}%
194      \cftpartfillnum{#2}%
195      \nobreak
196      \if@cfthaschapter
197          \global\nobreaktrue
198          \everypar{\global\nobreakfalse\everypar{}}
199      \else
200          \if@compatibility
201              \global\nobreaktrue
202              \everypar{\global\nobreakfalse\everypar{}}
203          \fi
204      \fi
205      \endgroup
206  \fi}
207 \fi

\cftbeforepartskip These are the user commands to control the typesetting of Part entries. They are
\cftpartnumwidth initialised to give the standard appearance.
\cftpfont 208 \if@cfthaspart
\cftpartpresnum 209 \newlength{\cftbeforepartskip}
\cftpartaftersnum 210 \setlength{\cftbeforepartskip}{2.25em \oplus \p0}
\cftpartaftersnumb 211 \newlength{\cftpartnumwidth}
\cftpartleader 212 \setlength{\cftpartnumwidth}{0em}
\cftpartdotsep 213 \newcommand{\cftpfont}{\large\bfseries}
\cftpartpagefont 214 \newcommand{\cftpartpresnum}{}
\cftpartaftersnum 215 \newcommand{\cftpartaftersnum}{}
\cftpartaftersnumb 216 \newcommand{\cftpartaftersnumb}{}
\cftpartindent 217 \newcommand{\cftpartleader}{\large\bfseries\cftdotfill{\cftpartdotsep}}
\cftpartfillnum 218 \newcommand{\cftpartdotsep}{\cftnodots}
219 \newcommand{\cftpartpagefont}{\large\bfseries}
220 \newcommand{\cftpartaftersnum}{}
221 \newlength{\cftpartindent}
222 \setlength{\cftpartindent}{0em}
223 \newcommand{\cftpartfillnum}[1]{%
224     {\cftpartleader}%
225     {\hb@xt@\pnumwidth{\hss {\cftpartpagefont #1}}}\cftpartaftersnum\par}
komma classes use some different settings.
226 \if@cftkoma
227 \setlength{\cftpartnumwidth}{2em}
228 \renewcommand{\cftpfont}{\sectfont\large}
229 \renewcommand{\cftpartpagefont}{\sectfont\large}
230 \fi
231 \fi
232

\l@chapter \l@chapter{<title>}{<page>} typesets the ToC entry for a chapter heading. It is
a parameterised copy of the default \l@chapter (see classes.dtx for the original
definition). This only applies to chaptered documents.

```

```

233 \if@cfthaschapter
234 \renewcommand*{\l@chapter}[2]{%
235   \ifnum \c@tocdepth >\m@ne
236     \addpenalty{-\@highpenalty}%
237     \vskip \cftbeforechapskip
238     {\leftskip \cftchapindent\relax
239      \rightskip \cftmarg
240      \parfillskip -\rightskip
241      \parindent \cftchapindent\relax\cfterindenttrue
242      \interlinepenalty\@M
243      \leavevmode
244      \tempdima \cftchapnumwidth\relax
245      \let\cftbsnum \cftappresnum
246      \let\cftasnum \cftchapafersnum
247      \let\cftasnumb \cftchapafersnumb
248      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
249      {\cftchapfont #1}\nobreak
250      \cftchapfillnum{#2}}
251   \fi}
252 \fi

```

\cftbeforechapskip These are the user commands to control the typesetting of Chapter entries. They  
 \cftchapindent are initialised to give the standard appearance.

```

\cftchapnumwidth 253 \if@cfthaschapter
  \cftchapfont 254 \newlength{\cftbeforechapskip}
  \cftappresnum 255 \setlength{\cftbeforechapskip}{1.0em \oplus\p@}
\cftchapafersnum 256 \newlength{\cftchapindent}
\cftchapafersnumb 257 \setlength{\cftchapindent}{0em}
  \cftchapleader 258 \newlength{\cftchapnumwidth}
  \cftchapdotsep 259 \setlength{\cftchapnumwidth}{1.5em}
\cftchappagefont 260 \newcommand{\cftchapfont}{\bfseries}
\cftchapafterpnum 261 \newcommand{\cftappresnum}{}
  \cftchapafersnum 262 \newcommand{\cftchapafersnum}{}
  \cftchapfillnum 263 \newcommand{\cftchapafersnumb}{}
  264 \newcommand{\cftchapleader}{\bfseries\cftdotfill{\cftchapdotsep}}
  265 \newcommand{\cftchapdotsep}{\cftnodots}
  266 \newcommand{\cftchappagefont}{\bfseries}
  267 \newcommand{\cftchapafterpnum}{}
  268 \newcommand{\cftchapfillnum}[1]{
  269   {\cftchapleader}\nobreak
  270   \hb@xt@\pnumwidth{\hfil\cftchappagefont #1}\cftchapafterpnum\par}

```

koma classes have different chapter settings.

```

271 \if@cfthakoma
272   \renewcommand{\cftchapfont}{\sectfont}
273 \fi
274 \fi
275

```

\l@section \l@section{\title}{\page} typesets the ToC entry for a **section** heading. It is

a parameterised copy of the default `\l@section` (see `classes.dtx` for the original definition).

```

276 \renewcommand*{\l@section}[2]{%
277   \ifnum \c@tocdepth >\z@
278     \if@cfthaschapter
279       \vskip \cftbeforesecskip
280     \else
281       \addpenalty\@secpenalty
282       \addvspace{\cftbeforesecskip}
283     \fi
284     {\leftskip \cftsecindent\relax
285      \rightskip \cftsecrmargin
286      \parfillskip -\rightskip
287      \parindent \cftsecindent\relax\cftsecafterindenttrue
288      \interlinepenalty\@M
289      \leavevmode
290      \cftsecnumwidth\relax
291      \let\cftbsnum \cftsecpresnum
292      \let\cftasnum \cftsecaftersnum
293      \let\cftasnumb \cftsecaftersnumb
294      \advance\leftskip \cftsecnumwidth\relax\cftsecrmargin
295      {\cftsecfont #1}\nobreak
296      \cftsecfillnum{#2}}
297   \fi}

```

`\cftbeforesecskip` These are the user commands to control the typesetting of Section entries. They  
`\cftsecindent` are initialised to give the standard appearance.

```

\cftsecnumwidth 298 \newlength{\cftbeforesecskip}
\cftsecfont 299 \newlength{\cftsecindent}
\cftsecpresnum 300 \newlength{\cftsecnumwidth}
\cftsecaftersnum 301 \newcommand{\cftsecpresnum}={}
\cftsecaftersnumb 302 \newcommand{\cftsecaftersnumb}={}
\cftsecleader 303 \newcommand{\cftsecaftersnumb}={}
\cftsecdotsep 304 \if@cfthaschapter
\cftsecpagefont 305 \setlength{\cftbeforesecskip}{\z@ \cftsecdotsep}
\cftsecafternum 306 \setlength{\cftsecindent}{1.5em}
\cftsecfillnum 307 \setlength{\cftsecnumwidth}{2.3em}
308 \newcommand{\cftsecfont}{\normalfont}
309 \newcommand{\cftsecleader}{\normalfont\cftdotfill{\cftsecdotsep}}
310 \newcommand{\cftsecdotsep}{\cftdotsep}
311 \newcommand{\cftsecpagefont}{\normalfont}
312 \else
313 \setlength{\cftbeforesecskip}{1.0em \cftsecdotsep}
314 \setlength{\cftsecindent}{0em}
315 \setlength{\cftsecnumwidth}{1.5em}
316 \newcommand{\cftsecfont}{\bfseries}
317 \newcommand{\cftsecleader}{\bfseries\cftdotfill{\cftsecdotsep}}
318 \newcommand{\cftsecdotsep}{\cftnodots}
319 \newcommand{\cftsecpagefont}{\bfseries}

```

```

320 \fi
321 \newcommand{\cftsecafterpnum}{}
322 \newcommand{\cftsecfillnum}[1]{%
323   {\cftsecleader}\nobreak
324   \hb@xt@\cftsecwidth{\hfil\cftsecpagefont #1}\cftsecafterpnum\par}
325

\l@subsection \l@subsection{\title}{\page} typesets the ToC entry for a subsection heading. It is a parameterised copy of the default \l@subsection (see classes.dtx for the original definition).
326 \renewcommand*{\l@subsection}[2]{%
  Only typeset the entry if it falls within the tocdepth.
327   \ifnum \c@tocdepth > @ne
    Add some vertical space.
328   \vskip \cftbeforesecskip
  Start a group to keep paragraphing changes local. Set the \leftskip to the entry's indentation.
329   {\leftskip \cftsubsecindent\relax
    Set the \rightskip to \@tocrmarg to leave room for the page number.
330   \rightskip \@tocrmarg
  Ensure that the last line of the entry will be filled. Setting \parfillskip to a negative number prevents any overfull box messages.
331   \parfillskip -\rightskip
  Set the paragraph indent to the entry's indentation.
332   \parindent \cftsubsecindent\relax\@afterindenttrue
  Try and prevent breaks between lines in a multiple line entry.
333   \interlinepenalty\@M
  Make sure that we have left vertical mode.
334   \leavevmode
  Our version of \numberline expects that the width of the number box is in \@tempdima, and that the three macros \@cftbsnum, \@cftasnum and \@cftasnumb are defined. We set all these to the values for this entry.
335   \@tempdima \cftsubsecnumwidth\relax
336   \let\@cftbsnum \cftsubsecpresnum
337   \let\@cftasnum \cftsubsecaftersnum
338   \let\@cftasnumb \cftsubsecaftersnumb
  Arrange that the (section number and) first line of the title is set at the current indent, and any further lines are further indented.
339   \advance\leftskip \@tempdima \null\nobreak\hskip -\leftskip
  Print the (number and) title, prohibiting any breaking.
340   {\cftsubsecfont #1}\nobreak

```



```

377      \let\@cftasnum \cftsubsubsecaftersnum
378      \let\@cftasnumb \cftsubsubsecaftersnumb
379      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
380      {\cftsubsubsecfont #1}\nobreak
381      \cftsubsubsecfillnum{#2}}
382  \fi}

\cftbeforesubsubsecskip These are the user commands to control the typesetting of Sub-sub-section entries.
\cftsubsubsecindent They are initialised to give the standard appearance.
\cftsubsubsecnumwidth 383 \newlength{\cftbeforesubsubsecskip}
\cftsubsubsecfont 384 \setlength{\cftbeforesubsubsecskip}{\z@ \plus .2\p@}
\cftsubsubsecpresnum 385 \newlength{\cftsubsubsecindent}
\cftsubsubsecaftersnum 386 \newlength{\cftsubsubsecnumwidth}
\cftsubsubsecaftersnumb 387 \if@cfthaschapter
\cftsubsubsecleader 388 \setlength{\cftsubsubsecindent}{7.0em}
\cftsubsubsecdotsep 389 \setlength{\cftsubsubsecnumwidth}{4.1em}
\cftsubsubsecpagefont 390 \else
\cftsubsubsecafterpnum 391 \setlength{\cftsubsubsecindent}{3.8em}
\cftsubsubsecfillnum 392 \setlength{\cftsubsubsecnumwidth}{3.2em}
393 \fi
394 \newcommand{\cftsubsubsecfont}{\normalfont}
395 \newcommand{\cftsubsubsecpresnum}{}
396 \newcommand{\cftsubsubsecaftersnum}{}
397 \newcommand{\cftsubsubsecaftersnumb}{}
398 \newcommand{\cftsubsubsecleader}{\normalfont\cftdotfill{\cftsubsubsecdotsep}}
399 \newcommand{\cftsubsubsecdotsep}{\cftdotsep}
400 \newcommand{\cftsubsubsecpagefont}{\normalfont}
401 \newcommand{\cftsubsubsecafterpnum}{}
402 \newcommand{\cftsubsubsecfillnum}[1]{%
403   {\cftsubsubsecleader}\nobreak
404   \hb@xt@\pnumwidth{\hfil\cftsubsubsecpagefont #1}\cftsubsubsecafterpnum\par}
405

\l@paragraph \l@paragraph{\langle title\rangle}{\langle page\rangle} typesets the ToC entry for a paragraph heading.
It is a parameterised copy of the default \l@paragraph (see classes.dtx for the
original definition).
406 \renewcommand*{\l@paragraph}[2]{%
407   \ifnum \c@tocdepth >3\relax
408     \vskip \cftbeforeparaskip
409     {\leftskip \cftparraindent\relax
410      \rightskip \cftcrmarg
411      \parfillskip -\rightskip
412      \parindent \cftparraindent\relax\cfterindenttrue
413      \interlinepenalty\@M
414      \leavevmode
415      \tempdima \cftparranumwidth\relax
416      \let\@cftbsnum \cftparrapresnum
417      \let\@cftasnum \cftparraaftersnum
418      \let\@cftasnumb \cftparraaftersnumb

```

```

419      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
420      {\cftparafont #1}\nobreak
421      \cftparafillnum{#2}
422  \fi}

\cftbeforeparaskip These are the user commands to control the typesetting of Paragraph entries.
\cftparaindent They are initialised to give the standard appearance.
\cftparanumwidth 423 \newlength{\cftbeforeparaskip}
\cftparafont 424 \setlength{\cftbeforeparaskip}{\z@ \plus.2\p@}
\cftparapresnum 425 \newlength{\cftparaindent}
\cftparaftersnum 426 \newlength{\cftparanumwidth}
\cftparaftersnum 427 \if@cfthaschapter
\cftparaleader 428 \setlength{\cftparaindent}{10em}
\cftparadotsep 429 \setlength{\cftparanumwidth}{5em}
\cftparapagefont 430 \else
\cftparafterpnum 431 \setlength{\cftparaindent}{7.0em}
\cftparafterpnum 432 \setlength{\cftparanumwidth}{4.1em}
\cftparafillnum 433 \fi
434 \newcommand{\cftparafont}{\normalfont}
435 \newcommand{\cftparapresnum}{}
436 \newcommand{\cftparaftersnum}{}
437 \newcommand{\cftparaftersnumb}{}
438 \newcommand{\cftparaleader}{\normalfont\cftdotfill{\cftparadotsep}}
439 \newcommand{\cftparadotsep}{\cftdotsep}
440 \newcommand{\cftparapagefont}{\normalfont}
441 \newcommand{\cftparafterpnum}{}
442 \newcommand{\cftparafillnum}[1]{%
443   {\cftparaleader}\nobreak
444   \hb@xt@\cftparafillnumwidth{\hfil\cftparapagefont #1}\cftparafterpnum\par}
445

\l@subparagraph \l@subparagraph{\langle title\rangle}{\langle page\rangle} typesets the ToC entry for a subparagraph heading. It is a parameterised copy of the default \l@subparagraph (see classes.dtx for the original definition).
446 \renewcommand*{\l@subparagraph}[2]{%
447   \ifnum \c@tocdepth >4\relax
448     \vskip \cftbeforesubparaskip
449     {\leftskip \cftsubparaindent\relax
450      \rightskip \cftocrmarg
451      \parfillskip -\rightskip
452      \parindent \cftsubparaindent\relax\cfterindenttrue
453      \interlinepenalty\@M
454      \leavevmode
455      \tempdima \cftsubparanumwidth\relax
456      \let\cftbsnum \cftsubparapresnum
457      \let\cftasnum \cftsubparaftersnum
458      \let\cftasnumb \cftsubparaftersnumb
459      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
460      {\cftsubparafont #1}\nobreak

```

```

461      \cftsubparafillnum{#2}}
462  \fi}

\cftbeforesubparaskip These are the user commands to control the typesetting of Sub-paragraph entries.
\cftsubparaindent They are initialised to give the standard appearance.
\cftsubparanumwidth 463 \newlength{\cftbeforesubparaskip}
\cftsubparafont    464  \setlength{\cftbeforesubparaskip}{\z@ \z@plus.2\p@}
\cftsubparapresnum 465 \newlength{\cftsubparaindent}
\cftsubparaftersnum 466 \newlength{\cftsubparanumwidth}
\cftsubparaftersnumb 467 \if@cfthaschapter
\cftsubparaleader   468  \setlength{\cftsubparaindent}{12em}
\cftsubparadotsep   469  \setlength{\cftsubparanumwidth}{6em}
\cftsubparapagefont 470 \else
\cftsubparafterpnum 471  \setlength{\cftsubparaindent}{10em}
\cftsubparafillnum   472  \setlength{\cftsubparanumwidth}{5em}
\cftsubparafillnum   473 \fi
\cftsubparafont     474 \newcommand{\cftsubparafont}{\normalfont}
\cftsubparapresnum  475 \newcommand{\cftsubparapresnum}{}
\cftsubparaftersnum 476 \newcommand{\cftsubparaftersnum}{}
\cftsubparaftersnumb 477 \newcommand{\cftsubparaftersnumb}{}
\cftsubparaleader   478 \newcommand{\cftsubparaleader}{\normalfont\cftdotfill{\cftsubparadotsep}}
\cftsubparadotsep   479 \newcommand{\cftsubparadotsep}{\cftdotsep}
\cftsubparapagefont 480 \newcommand{\cftsubparapagefont}{\normalfont}
\cftsubparaafterpnum 481 \newcommand{\cftsubparaafterpnum}{}
\cftsubparafillnum   482 \newcommand{\cftsubparafillnum}[1]{%
\cftsubparaleader\nobreak
\hb@xt@\cftsubparafillnumwidth{\hfil\cftsubparapagefont #1}\cftsubparaafterpnum\par}
483
484
485

\@cftdobiblof If the tocbibind package has been used and it has redefined \listoffigures we
need to cater for that. The contents of the definition are defined in tocbibind.
486 \newcommand{\@cftdobiblof}{%
487  \if@dotoclof
488  \if@bibchapter
489    \phantomsection
490    \addcontentsline{toc}{chapter}{\listfigurename}
491  \else
492    \phantomsection
493    \addcontentsline{toc}{\@tocextra}{\listfigurename}
494  \fi
495 \fi}
496

\listoffigures This is a parameterised version of the default \listoffigures command. The
changes are postponed until after all packages have been loaded. Each class has
its own definition, but we have to cater for all classes in one definition, hence some
of the checks. First, perform the default checks for multicolumns. (Do nothing if
titles option is used).
497 \AtBeginDocument{

```

```

498 \if@cftnctoc\else
499 \renewcommand{\listoffigures}{%
500   \cfttocstart

```

Ensure that any previous paragraph has been finished. Within a group set the local paragraphing style. Typeset the title and then do the contents of the .lof file.

```

501   \par
502   \begingroup
503     \parindent\z@\parskip\cftparskip
504     \cftmakeloftitle
505     \if@cfttocbibind
506       \cftdobiblof
507     \fi
508     \cftstarttoc{lof}%
509   \endgroup

```

Finally, restore any multicolumn typesetting.

```

510   \cfttocfinish}
511 \fi
512 }
513

```

**\cftmakeloftitle** This command typesets the title for the LoF.

```

514 \newcommand{\cftmakeloftitle}{%
515   \addpenalty\secpenalty
516   \if@cfthaschapter
517     \vspace*\cftbeforeloftitleskip
518   \else
519     \vspace{\cftbeforeloftitleskip}
520   \fi
521   \cftpagestyle
522   {\interlinepenalty\OM
523   {\cftloftitlefont\listfigurename}\cftafterloftitle}
524   \cftmarklof
525   \par\nobreak
526   \vskip \cftafterloftitleskip
527   \cftafterheading}
528

```

**\cftbeforeloftitleskip** These two lengths control the vertical spacing before and after the LoF title.

```

529 \newlength{\cftbeforeloftitleskip}
530 \newlength{\cftafterloftitleskip}

```

Their values depend on whether the document has chapters or not. In chaptered documents the default LoF title is typeset as a **\chapter\***, otherwise as a **\section\***.

```

531 \if@cfthaschapter
532   \setlength{\cftbeforeloftitleskip}{50pt}
533   \setlength{\cftafterloftitleskip}{40pt}

```

```

534 \else
535   \setlength{\cftbeforeloftitleskip}{3.5ex \@plus 1ex \@minus .2ex}
536   \setlength{\cftafterloftitleskip}{2.3ex \@plus .2ex}
537 \fi

\cftloftitlefont The LoF title is typeset in the style given by \cftloftitlefont. The macro
\cftafterloftitle \cftafterloftitle is called after typesetting the title. This is initialised to do
nothing. Both these macros can be redefined to do other things (e.g., adding an
\hfill to \cftloftitlefont will make the title flushright).

538 \if@cfthaschapter
539   \newcommand{\cftloftitlefont}{\normalfont\Huge\bfseries}
540   \if@cftkoma\renewcommand{\cftloftitlefont}{\size@chapter\sectfont}\fi
541 \else
542   \newcommand{\cftloftitlefont}{\normalfont\Large\bfseries}
543   \if@cftkoma\renewcommand{\cftloftitlefont}{\size@section\sectfont}\fi
544 \fi
545 \newcommand{\cftafterloftitle}{}  

546

\l@figure \l@figure{<title>}{<page>} typesets the LoF entry for a figure caption heading.
It is a parameterised copy of the default \l@figure (see classes.dtx for the
original definition).

547 \renewcommand*{\l@figure}[2]{%
548   \ifnum \c@lofdepth >\z@
549     \vskip \cftbeforefigskip
550     {\leftskip \cftfigindent\relax
551      \rightskip \cftcrmarg
552      \parfillskip -\rightskip
553      \parindent \cftfigindent\relax\cftafterindenttrue
554      \interlinepenalty\cftinterlinepenalty
555      \leavevmode
556      \cftfignumwidth\relax
557      \let\cftbsnum \cftfigpresnum
558      \let\cftasnum \cftfigaftersnum
559      \let\cftasnumb \cftfigaftersnumb
560      \advance\leftskip \cftfignumwidth\relax\cftfigaftersnumb\relax
561      {\cftfigfont #1}\nobreak
562      \cftfigfillnum{#2}}
563   \fi
564 }

\cftbeforefigskip These are the user commands to control the typesetting of Figure caption entries.
\cftfigindent They are initialised to give the standard appearance.

\cftfignumwidth 565 \newlength{\cftbeforefigskip}
\cftfigfont 566   \setlength{\cftbeforefigskip}{\z@ \@plus .2\p@}
\cftfigpresnum 567 \newlength{\cftfigindent}
\cftfigaftersnum 568   \setlength{\cftfigindent}{1.5em}
\cftfigaftersnumb 569 \newlength{\cftfignumwidth}
\cftfigleader 570   \setlength{\cftfignumwidth}{2.3em}
\cftfigdotsep
\cftfigpagefont
\cftfigafterpnum
\cftfigfillnum

```

```

571 \newcommand{\cftfigfont}{\normalfont}
572 \newcommand{\cftfigpresnum}{}
573 \newcommand{\cftfigaftersnum}{}
574 \newcommand{\cftfigaftersnumb}{}
575 \newcommand{\cftfigleader}{\normalfont\cftdotfill{\cftfigdotsep}}
576 \newcommand{\cftfigdotsep}{\cftdotsep}
577 \newcommand{\cftfigpagefont}{\normalfont}
578 \newcommand{\cftfigafterpnum}{}
579 \newcommand{\cftfigfillnum}[1]{%
580   {\cftfigleader}\nobreak
581   \hb@xt@{\pnumwidth{\hfil\cftfigpagefont #1}}{\cftfigafterpnum\par}
582

```

**lofdepth** The counters `lofdepth` and `lotdepth` are defined by the `subfigure` package. Define `lotdepth` them here if that package is not used.

```

583 \if@cftsubfigopt\else
584   \newcounter{lofdepth}\setcounter{lofdepth}{1}
585   \newcounter{lotdepth}\setcounter{lotdepth}{1}
586 \fi
587

```

**\@cftdobiblot** If the `tocbibind` package has been used and it has redefined `\listoftables` we need to cater for that. The contents of the definition are defined in `tocbibind`.

```

588 \newcommand{\@cftdobiblot}{%
589   \if@dotoclot
590     \if@bibchapter
591       \phantomsection
592       \addcontentsline{toc}{chapter}{\listtablename}
593     \else
594       \phantomsection
595       \addcontentsline{toc}{\@tocextra}{\listtablename}
596     \fi
597   \fi}
598

```

**\listoftables** This is a parameterised version of the default `\listoftables` command. The changes are postponed until after all packages have been loaded. Each class has its own definition, but we have to cater for all classes in one definition, hence some of the checks. First, perform the default checks for multicolumns. (Do nothing if the `titles` option has been used).

```

599 \AtBeginDocument{
600 \if@cftnctoc\else
601 \renewcommand{\listoftables}{%
602   \@cfttocstart

```

Ensure that any previous paragraph has been finished. Within a group set the local paragraphing style. Typeset the title and then do the contents of the `.lot` file.

```

603   \par

```

```

604  \begingroup
605    \parindent\z@ \parskip\cftparskip
606    \cftmakelottitle
607    \if@cfttocbibind
608      \cftdobiblot
609    \fi
610    \cftstarttoc{lot}%
611  \endgroup

```

Finally, restore any multicolumn typesetting.

```

612  \cfttocfinish}
613 \fi
614 }
615

```

**\cftmakelottitle** This command typesets the title for the LoT.

```

616 \newcommand{\cftmakelottitle}{%
617   \addpenalty\secpenalty
618   \if@cfthaschapter
619     \vspace*\cftbeforelottitleskip
620   \else
621     \vspace\cftbeforelottitleskip
622   \fi
623   \cftpagestyle
624   {\interlinepenalty\relax
625   {\cftlottitlefont\listtablename}\cftafterlottitle}
626   \cftmarklot
627   \par\nobreak
628   \vskip\cftafterlottitleskip
629   \cftafterheading}
630

```

**\cftbeforelottitleskip** These two lengths control the vertical spacing before and after the LoT title.

**\cftafterlottitleskip**

```

631 \newlength{\cftbeforelottitleskip}
632 \newlength{\cftafterlottitleskip}

```

Their values depend on whether the document has chapters or not. In chaptered documents the default LoT title is typeset as a **\chapter\***, otherwise as a **\section\***.

```

633 \if@cfthaschapter
634   \setlength{\cftbeforelottitleskip}{50pt}
635   \setlength{\cftafterlottitleskip}{40pt}
636 \else
637   \setlength{\cftbeforelottitleskip}{3.5ex \oplus 1ex \ominus .2ex}
638   \setlength{\cftafterlottitleskip}{2.3ex \oplus .2ex}
639 \fi

```

**\cftlottitlefont** The LoT title is typeset in the style given by **\cftlottitlefont**. The macro **\cftafterlottitle** **\cftafterlottitle** is called after typesetting the title. This is initialised to do

nothing. Both these macros can be redefined to do other things (e.g., adding an `\hfill` to `\cftlottitlefont` will make the title flushright).

```

640 \if@cfthaschapter
641   \newcommand{\cftlottitlefont}{\normalfont\Huge\bfseries}
642   \if@cftkoma\renewcommand{\cftlottitlefont}{\size@chapter\sectfont}\fi
643 \else
644   \newcommand{\cftlottitlefont}{\normalfont\Large\bfseries}
645   \if@cftkoma\renewcommand{\cftlottitlefont}{\size@section\sectfont}\fi
646 \fi
647 \newcommand{\cftafterlottitle}{}  

648

```

`\l@table` `\l@table{<title>}{<page>}` typesets the LoT entry for a `table` caption heading. It is a parameterised copy of the default `\l@table` (see `classes.dtx` for the original definition).

```

649 \renewcommand*{\l@table}[2]{%
650   \ifnum\c@lotdepth >\z@
651     \vskip \cftbeforetabskip
652     {\leftskip \cfttabindent\relax
653      \rightskip \cftcrmarg
654      \parfillskip -\rightskip
655      \parindent \cfttabindent\relax\cftafterindenttrue
656      \interlinepenalty\@M
657      \leavevmode
658      \cfttabnumwidth\relax
659      \let\cftbsnum \cfttabpresnum
660      \let\cftasnum \cfttabaftersnum
661      \let\cftasnumb \cfttabaftersnumb
662      \advance\leftskip \cfttabnumwidth\relax\nobreak\hskip -\leftskip
663      {\cfttabfont #1}\nobreak
664      \cfttabfillnum{#2}}
665   \fi
666 }

```

`\cftbeforetabskip` These are the user commands to control the typesetting of Table caption entries.  
`\cfttabindent` They are initialised to give the standard appearance.

```

\cfttabnumwidth 667 \newlength{\cftbeforetabskip}
\cfttabfont 668 \setlength{\cftbeforetabskip}{\z@ \cplus .2\p@}
\cfttabpresnum 669 \newlength{\cfttabindent}
\cfttabaftersnum 670 \setlength{\cfttabindent}{1.5em}
\cfttabaftersnumb 671 \newlength{\cfttabnumwidth}
\cfttabaftersnumb
\cfttableader 672 \setlength{\cfttabnumwidth}{2.3em}
\cfttabdotsep 673 \newcommand{\cfttabfont}{\normalfont}
\cfttabpagefont 674 \newcommand{\cfttabpresnum}{}
\cfttabaftersnum 675 \newcommand{\cfttabaftersnum}{}
\cfttabaftersnumb 676 \newcommand{\cfttabaftersnumb}{}
\cfttabfillnum 677 \newcommand{\cfttableader}{\normalfont\cftdotfill{\cfttabdotsep}}
\cfttabdotsep 678 \newcommand{\cfttabdotsep}{\cftdotsep}
\cfttabpagefont 679 \newcommand{\cfttabpagefont}{\normalfont}

```

```

680 \newcommand{\cfttabafterpnum}{}%
681 \newcommand{\cfttabfillnum}[1]{%
682   {\cftableader}\nobreak
683   \hb@xt@{\pnumwidth{\hfil\cfttabpagefont #1}}{\cfttabafterpnum\par}
684

```

### 3.1 Support for the `subfigure` package

The code for supporting the `subfigure` package is, in all essentials, the same as that for the figure and table captions; only the names are changed. However, the code need only be executed if the `subfigure` package is actually loaded.

`\@cftl@subfig` This command redefines the `\l@subfigure` command.

```
685 \newcommand{\@cftl@subfig}{%
```

`\l@subfigure` `\l@subfigure{<title>}{<page>}` typesets the LoF entry for a `subfigure` caption heading. It is essentially the same as the parameterised code for `\l@figure` except that account has to be taken of `lofdepth`.

```

686 \renewcommand*{\l@subfigure}[2]{%
687   \ifnum \c@lofdepth > \toclevel@subfigure
688     \vskip \cftbeforesubfigskip
689     {\leftskip \cftsubfigindent\relax
690      \rightskip \cftsubfigmarg
691      \parfillskip -\rightskip
692      \parindent \cftsubfigindent\relax\cfterindenttrue
693      \interlinepenalty\@M
694      \leavevmode
695      \tempdima \cftsubfignumwidth\relax
696      \let\cftbsnum \cftsubfigpresnum
697      \let\cftasnum \cftsubfigaftersnum
698      \let\cftasnumb \cftsubfigaftersnumb
699      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
700      {\cftsubfigfont ##1}\nobreak
701      \cftsubfigfillnum##2}
702   \fi
703 }
704 }
```

705

`\@cftsetsubfig` This command initialises the setup for subfigure captions in the LoF.

```
706 \newcommand{\@cftsetsubfig}{%
```

```

\cftbeforesubfigskip
\cftsubfigindent 707 \newlength{\cftbeforesubfigskip}
\cftsubfignumwidth 708 \setlength{\cftbeforesubfigskip}{\z@ \cplus .2\p@}
\cftsubfigfont 709 \newlength{\cftsubfigindent}
\cftsubfigpresnum 710 \setlength{\cftsubfigindent}{3.8em}
\cftsubfigaftersnum 711 \newlength{\cftsubfignumwidth}
\cftsubfigaftersnumb 712 \setlength{\cftsubfignumwidth}{2.5em}

\cftsubfigleader
\cftsubfigdotsep
\cftsubfigpagefont
\cftsubfigafterpnum
\toclevel@subfig
\cftsubfigfillnum
```

```

713 \newcommand{\cftsubfigfont}{\normalfont}
714 \newcommand{\cftsubfigpresnum}{}
715 \newcommand{\cftsubfigaftersnum}{}
716 \newcommand{\cftsubfigaftersnumb}{}
717 \newcommand{\cftsubfigleader}{\normalfont\cftdotfill{\cftsubtabdotsep}}
718 \newcommand{\cftsubfigdotsep}{\cftdotsep}
719 \newcommand{\cftsubfigpagefont}{\normalfont}
720 \newcommand{\cftsubfigafterpnum}{}
721 \providecommand{\toclevel@subfigure}{1}
722 \newcommand{\cftsubfigfillnum}[1]{%
723   {\cftsubfigleader}\nobreak
724   \hb@xt@{\cftsubfigwidth{\hfil\cftsubfigpagefont ##1}\cftsubfigafterpnum\par}

```

This is the end of \@cftsetsubfig.

```

725 }
726

```

\@cftl@subtab This code redefines the code for \l@subtable.

```

727 \newcommand{\@cftl@subtab}{
```

\l@subtable \l@subtable{\langle title\rangle}{\langle page\rangle} typesets the LoT entry for a **subtable** caption heading. It is essentially the same as the parameterised code for \l@table except account has to be taken of *lotdepth*.

```

728 \renewcommand*{\l@subtable}[2]{%
729   \ifnum \c@lotdepth > \toclevel@subtable
730     \vskip \cftbeforesubtabskip
731     {\leftskip \cftsubtabindent\relax
732      \rightskip \cftcrmarg
733      \parfillskip -\rightskip
734      \parindent \cftsubtabindent\relax\cfterindenttrue
735      \interlinepenalty\OM
736      \leavevmode
737      \tempdima \cftsubtabnumwidth\relax
738      \let\cftbsnum \cftsubtabpresnum
739      \let\cftasnum \cftsubtabaftersnum
740      \let\cftasnumb \cftsubtabaftersnumb
741      \advance\leftskip \tempdima \null\nobreak\hskip -\leftskip
742      {\cftsubtabfont ##1}\nobreak
743      \cftsubtabfillnum{##2}}
744   \fi
745 }
746 }
```

\@cftsetsubtab This command sets up the defaults for subtable entries in the LoT.

```

747 \newcommand{\@cftsetsubtab}{
```

\cftbeforesubtabskip These are the user commands to control the typesetting of Subtable caption entries. They are initialised to give the standard appearance.

\cftsubtabwidth 748 \newlength{\cftbeforesubtabskip}

\cftsubtabfont

\cftsubtabpresnum

\cftsubtabaftersnum

\cftsubtabaftersnumb

\cftsubtableader

\cftsubtabdotsep

\cftsubtabpagefont

\cftsubtabafterpnum

\toclevel@subtable

\cftsubtabfillnum

```

749 \setlength{\cftbeforesubtabskip}{\z@ \oplus .2\p@}
750 \newlength{\cftsubtabindent}
751 \setlength{\cftsubtabindent}{3.8em}
752 \newlength{\cftsubtabnumwidth}
753 \setlength{\cftsubtabnumwidth}{2.5em}
754 \newcommand{\cftsubtabfont}{\normalfont}
755 \newcommand{\cftsubtabpresnum}{}
756 \newcommand{\cftsubtabaftersnum}{}
757 \newcommand{\cftsubtabaftersnumb}{}
758 \newcommand{\cftsubtableader}{\normalfont\cftdotfill{\cftsubabdotsep}}
759 \newcommand{\cftsubabdotsep}{\cftdotsep}
760 \newcommand{\cftsubtabpagefont}{\normalfont}
761 \newcommand{\cftsubtabafterpnum}{}
762 \providecommand{\toclevel@subtable}{1}
763 \newcommand{\cftsubabfillnum}[1]{%
764 {\cftsubtableader}\nobreak
765 \hb@xt@\pnumwidth{\hfil\cftsubtabpagefont ##1}\cftsubtabafterpnum\par}

```

This is the end of \cftsetsubtab.

```

766 }
767
```

Call the `subfigure` package setup code only if the `subfigure` option is specified.  
The `\l@...` redefinitions have to come after the `subfigure` package is loaded.

```

768
769 \if@cftsubfigopt
770   \cftsetsubfig\cftsetsubtab
771   \AtBeginDocument{\cftl@subfig\cftl@subtab}
772 \fi
773 %% \AtBeginDocument{\if@cftsubfigopt
774 %%   \cftsetsubfig\cftsetsubtab
775 %%   \cftl@subfig\cftl@subtab
776 %% \fi}
777
```

### 3.2 New list of...

`\newlistentry` `\newlistentry[<within>]{<counter>}[<ext>]{<level-1>}` creates a set of commands for a new kind of entry into a List of.

```

778 \newcommand{\newlistentry}[4][\empty{}]{%
```

`\c@X` Check if `<within>` and `<counter>` have been defined. It is an error if `<within>` has not  
`\theX` been defined, and an error if `<counter>` has been defined. Set the default counter values.

```

779 \c@ifundefined{c@#2}{%      check & set the counter
780   \ifx \empty\relax
781     \newcounter{#2}
782   \else
783     \c@ifundefined{c@#1}{\PackageWarning{tocloft}{%
```

```

784          {#1 has no counter for use as a 'within'}
785          \newcounter{#2}%
786          {\newcounter{#2}[#1]%
787          \expandafter\edef\csname the#2\endcsname{%
788          \expandafter\noexpand\csname the#1\endcsname.\noexpand\arabic{#2}}}
789      \fi
790      \setcounter{#2}{0}
791  }
792 {\PackageError{tocloft}{#2 has been previously defined}{\@eha}}
793

```

That finishes off the error checking. No matter what the result, the rest of the new commands are defined.

\l@X \l@X{\langle title\rangle}{\langle page\rangle} typesets the entry.

```
794  \@namedef{l@#2}##1##2%
```

Only typeset if the \Zdepth is greater than \langle level-1\rangle.

```

795  \ifnum \@nameuse{c@#3depth} > #4\relax
796    \vskip \nameuse{cftbefore#2skip}
797    {\leftskip \nameuse{cft#2indent}\relax
798    \rightskip \nameuse{cftmarg}
799    \parfillskip -\rightskip
800    \parindent \nameuse{cft#2indent}\relax\afterindenttrue
801    \interlinepenalty\OM
802    \leavevmode
803    \tempdima \nameuse{cft#2numwidth}\relax
804    \expandafter\let\expandafter\cftbsnum\csname cft#2presnum\endcsname
805    \expandafter\let\expandafter\cftasnum\csname cft#2aftersnum\endcsname
806    \expandafter\let\expandafter\cftasnumb\csname cft#2aftersnumb\endcsname
807    \advance\leftskip@\tempdima \null\nobreak\hskip -\leftskip
808    {\nameuse{cft#2font}##1}\nobreak
809    \nameuse{cft#2fillnum}##2}
810  \fi
811 } % end of \l@X
812

```

Now define all the layout commands used by \l@X. The default values of these correspond to those for section entries in non-chaptered documents.

\cftbeforeXskip

```
813  \expandafter\newlength\csname cftbefore#2skip\endcsname
814  \setlength{\nameuse{cftbefore#2skip}}{\z@ \oplus .2\p@}
```

\cftXindent

```
\cftXnumwidth 815  \expandafter\newlength\csname cft#2indent\endcsname
816  \expandafter\newlength\csname cft#2numwidth\endcsname
```

Set the default values for the indent and numwidth depending on the entry's level. A level of 1 corresponds to a figure entry.

```

817 \ifcase #4\relax % 0
818   \setlength{\@nameuse{cft#2indent}}{0em}
819   \setlength{\@nameuse{cft#2numwidth}}{1.5em}
820 \or % 1
821   \setlength{\@nameuse{cft#2indent}}{1.5em}
822   \setlength{\@nameuse{cft#2numwidth}}{2.3em}
823 \or % 2
824   \setlength{\@nameuse{cft#2indent}}{3.8em}
825   \setlength{\@nameuse{cft#2numwidth}}{3.2em}
826 \or % 3
827   \setlength{\@nameuse{cft#2indent}}{7.0em}
828   \setlength{\@nameuse{cft#2numwidth}}{4.1em}
829 \else % anything else
830   \setlength{\@nameuse{cft#2indent}}{10.0em}
831   \setlength{\@nameuse{cft#2numwidth}}{5.0em}
832 \fi

```

\cftXfont And the remaining commands.

```

\cftXpresnum 833 \@namedef{cft#2font}{\normalfont}
\cftXaftersnum 834 \@namedef{cft#2presnum}{}
\cftXaftersnumb 835 \@namedef{cft#2aftersnum}{}
\cftXdotsep 836 \@namedef{cft#2aftersnumb}{}
\cftXleader 837 \@namedef{cft#2dotsep}{\cftdotsep}
\cftXpagefont 838 \@namedef{cft#2leader}{\normalfont\cftdotfill{\@nameuse{cft#2dotsep}}}
\cftXafterpnum 839 \@namedef{cft#2pagefont}{\normalfont}
\cftXafterpnum 840 \@namedef{cft#2afterpnum}{}

```

\toclevel@X The hyperref package needs a command \toclevel@X, holding the  $\langle level-1 \rangle$  value.

```

841 \@namedef{toclevel@#2}{#4}

```

\cftXfillnum Typeset the leader and page number.

```

842 \@namedef{cft#2fillnum}##1{%
843   {\@nameuse{cft#2leader}}\nobreak
844   \hb@xt@{\cftdotwidth{\hfil}\@nameuse{cft#2pagefont}##1}\@nameuse{cft#2afterpnum}\par}

```

This ends the definition of \newlistentry.

```

845 } % end \newlistentry
846

```

\newlistof \newlistof[ $\langle within \rangle$ ]{ $\langle counter \rangle$ }{ $\langle ext \rangle$ }{ $\langle listofname \rangle$ } creates the commands for a new List of.

```

847 \newcommand{\newlistof}[4][\empty] {%

```

Call \newlistentry to set up the first level entry.

```

848   \ifx \empty#1\relax
849     \newlistentry[#2]{#3}{0}
850   \else
851     \newlistentry[#1]{#2}{#3}{0}
852   \fi
853

```

```

\ext@Z The file extension and listing depth.
\Zdepth 854  \@namedef{ext@#3}{#3}
          855  \newcounter{#3depth}
          856  \setcounter{#3depth}{1}
          857

\cftmarkZ The heading marks for the listing.
858  \if@cftkoma
859    \@namedef{cftmark#3}{%
860      \@mkboth{#4}{#4}}
861  \else
862    \@namedef{cftmark#3}{%
863      \@mkboth{\MakeUppercase{#4}}{\MakeUppercase{#4}}}
864  \fi

\listofX Typeset the listing title and entries.
865  \if@cftnctoc
For the titles option, basically copy the code from the standard \tableofcontents command.
866  \@namedef{listof#2}{%
867    \@cfttocstart
868    \if@cfthaschapter
869      \chapter*{#4}
870    \else
871      \section*{#4}
872    \fi
873    \@nameuse{cftmark#3}
874    \@starttoc{#3}%
875    \@cfttocfinish}
876  \else
Otherwise use the fully parameterised definition.
877  \@namedef{listof#2}{%
878    \@cfttocstart
879    \par
880    \begingroup
881      \parindent\z@ \parskip\cftparskip
882      \@nameuse{@cftmake#3title}
883      \@starttoc{#3}%
884    \endgroup
885    \@cfttocfinish}
886  \fi
887

\@cftmakeZtitle Typeset the title.
888  \@namedef{@cftmake#3title}{%
889    \addpenalty\@secpenalty
890    \if@cfthaschapter
891      \vspace*{\@nameuse{cftbefore#3titleskip}}}
```

```

892     \else
893         \vspace{\@nameuse{cftbefore#3titleskip}}
894     \fi
895     \cftpagestyle
896     {\interlinepenalty\@M
897     {\@nameuse{cft#3titlefont}\#4}{\@nameuse{cftafter#3title}}
898     \cftmark#3}
899     \par\nobreak
900     \vskip \cftafter#3titleskip
901     \cftafterheading}
902

\cftbeforeZtitleskip  The skips before and after the title heading, and the title font. The default values
\cftafterZtitleskip  depend on whether or not the document class has chapters.
\cftZtitlefont 903   \expandafter\newlength\csname cftbefore#3titleskip\endcsname
904   \expandafter\newlength\csname cftafter#3titleskip\endcsname
905   \if@cfthaschapter
906       \setlength{\@nameuse{cftbefore#3titleskip}}{50pt}
907       \setlength{\@nameuse{cftafter#3titleskip}}{40pt}
908       \if@cftkoma
909           \namedef{cft#3titlefont}{\size@chapter\sectfont}
910       \else
911           \namedef{cft#3titlefont}{\normalfont\Huge\bfseries}
912       \fi
913   \else
914       \setlength{\@nameuse{cftbefore#3titleskip}}{3.5ex \@plus 1ex \@minus .2ex}
915       \setlength{\@nameuse{cftafter#3titleskip}}{2.3ex \@plus .2ex}
916       \if@cftkoma
917           \namedef{cft#3titlefont}{\size@section\sectfont}
918       \else
919           \namedef{cft#3titlefont}{\normalfont\Huge\bfseries}
920       \fi
921   \fi

\cftafterZtitle  Something to go after the title.
922   \namedef{cftafter#3title}{}}

This is the end of the definition of \newlistof.
923 } % end \newlistof
924

\cftsetindents  \cftsetindents{\<entry>}{\<indent>}{\<numwidth>} sets the indent and numwidth
for entry <entry>. The macro has to map between the external entry name and
the internal shorthand.
925 \newcommand{\cftsetindents}[3]{%
926   \def\@cftemp{\#1}
927   \ifx\@cftemp\cftchapname
928     \cftsetindents{chap}{\#2}{\#3}
929   \else

```

```

930      \ifx\@cftemp\cftsecname \@cftsetindents{sec}{#2}{#3}
931      \else
932          \ifx\@cftemp\cftsubsecname \@cftsetindents{subsec}{#2}{#3}
933          \else
934              \ifx\@cftemp\cftsubsubsecname \@cftsetindents{subsubsec}{#2}{#3}
935              \else
936                  \ifx\@cftemp\cftparaname \@cftsetindents{para}{#2}{#3}
937                  \else
938                      \ifx\@cftemp\cftsubparaname \@cftsetindents{subpara}{#2}{#3}
939                      \else
940                          \ifx\@cftemp\cftfigname \@cftsetindents{fig}{#2}{#3}
941                          \else
942                              \ifx\@cftemp\cftsubfigname \@cftsetindents{subfig}{#2}{#3}
943                              \else
944                                  \ifx\@cftemp\cfttabname \@cftsetindents{tab}{#2}{#3}
945                                  \else
946                                      \ifx\@cftemp\cftsubtabname \@cftsetindents{subtab}{#2}{#3}
947                                      \else
948                                          \@cftsetindents{#1}{#2}{#3}
949                                          \fi
950                                          \fi
951                                          \fi
952                                          \fi
953                                          \fi
954                                          \fi
955                                          \fi
956                                          \fi
957                                          \fi
958                                          \fi
959 }
960

\@cftsetindents \@cftsetindents{\langle X\rangle}{\langle indent\rangle}{\langle numwidth\rangle} is the internal version of \cftsetindents, where in this case \langle X\rangle is the internal (shorthand) name of the entry.
961 \newcommand{\@cftsetindents}[3]{%
962     \setlength{\@nameuse{cft#1indent}}{#2}
963     \setlength{\@nameuse{cft#1numwidth}}{#3}
964 }
965

```

### 3.3 Switching page numbering

```

\@cftpnumoff \@cftpnumoff{\langle shorthand\rangle} is the workhorse for switching page numbering off. The \langle shorthand\rangle argument is the shorthand name of the entry (e.g. subsec for subsection). The macro redefines the \cftXnumfill command so that there is no leader and the page number is ignored.
966 \newcommand{\@cftpnumoff}[1]{%
967     \@namedef{cft#1fillnum}##1{%
968         \cftpfillskip\@nameuse{cft#1afterpnum}\par}}

```

969

```
\cftchapname Unfortunately an early design decision was the use shorthands like sec for
\cftsecname section. For the page switching I need to be able to correlate the shorthands
\cftsubsecname and longhands.

\cftsubsubsecname 970 \newcommand*{\cftchapname}{chapter}
\cftparaname 971 \newcommand*{\cftsecname}{section}
\cftsubparaname 972 \newcommand*{\cftsubsecname}{subsection}
\cftfigname 973 \newcommand*{\cftsubsubsecname}{subsubsection}
\cftsubfigname 974 \newcommand*{\cftparaname}{paragraph}
\cfttabname 975 \newcommand*{\cftsubparaname}{subparagraph}
\cftsubtabname 976 \newcommand*{\cftfigname}{figure}
977 \newcommand*{\cftsubfigname}{subfigure}
978 \newcommand*{\cfttabname}{table}
979 \newcommand*{\cftsubtabname}{subtable}
980

\cftpagenumbersoff 981 The user level command for switching off page numbers is \cftpagenumbersoff{(entry)}
where (entry) is the longhand name of the entry. The principal task opf this macro
is to determine the corresponding shorthand name of the (entry) and then call
\@cftpnumoff to do the work. For part and user-defined entries the long- and
short-hand entry names are identical.

981 \DeclareRobustCommand{\cftpagenumbersoff}[1]{%
982   \def\@cftemp{#1}
983   \ifx\@cftemp\cftchapname
984     \@cftpnumoff{chap}
985   \else
986     \ifx\@cftemp\cftsecname \@cftpnumoff{sec}
987   \else
988     \ifx\@cftemp\cftsubsecname \@cftpnumoff{subsec}
989   \else
990     \ifx\@cftemp\cftsubsubsecname \@cftpnumoff{subsubsec}
991   \else
992     \ifx\@cftemp\cftparaname \@cftpnumoff{para}
993   \else
994     \ifx\@cftemp\cftsubparaname \@cftpnumoff{subpara}
995   \else
996     \ifx\@cftemp\cftfigname \@cftpnumoff{fig}
997   \else
998     \ifx\@cftemp\cftsubfigname \@cftpnumoff{subfig}
999   \else
1000     \ifx\@cftemp\cfttabname \@cftpnumoff{tab}
1001   \else
1002     \ifx\@cftemp\cftsubtabname \@cftpnumoff{subtab}
1003   \else
1004     \@cftpnumoff{#1}
1005   \fi
1006   \fi
1007   \fi
1008 }
```

```

1008          \fi
1009          \fi
1010          \fi
1011          \fi
1012          \fi
1013          \fi
1014      \fi
1015 }
1016

\cftpagenumberson \cftpagenumberson{\langle entry\rangle} is the user level command for reversing the corre-
sponding \cftpagenumbersoff.

1017 \DeclareRobustCommand{\cftpagenumberson}[1]{%
1018   \def\@cftemp{\#1}
1019   \ifx\@cftemp\cftchapname
1020     \cftpnumon{chap}
1021   \else
1022     \ifx\@cftemp\cftsecname \cftpnumon{sec}
1023   \else
1024     \ifx\@cftemp\cftsubsecname \cftpnumon{subsec}
1025   \else
1026     \ifx\@cftemp\cftsubsubsecname \cftpnumon{subsubsec}
1027   \else
1028     \ifx\@cftemp\cftparaname \cftpnumon{para}
1029   \else
1030     \ifx\@cftemp\cftsubparaname \cftpnumon{subpara}
1031   \else
1032     \ifx\@cftemp\cftfigname \cftpnumon{fig}
1033   \else
1034     \ifx\@cftemp\cftsubfigname \cftpnumon{subfig}
1035   \else
1036     \ifx\@cftemp\cfttabname \cftpnumon{tab}
1037   \else
1038     \ifx\@cftemp\cftsubtabname \cftpnumon{subtab}
1039   \else
1040     \cftpnumon{\#1}
1041   \fi
1042   \fi
1043   \fi
1044   \fi
1045   \fi
1046   \fi
1047   \fi
1048   \fi
1049   \fi
1050   \fi
1051 }
1052

```

\cftpnumon \cftpnumon{\langle shorthand\rangle} is the workhorse for switching page numbering off.

The `<shorthand>` argument is the shorthand name of the entry (e.g. `subsec` for `subsection`). The macro defines the `\cftXnumfill` command to correspond to the default definition.

```
1053 \newcommand{\cftpnumon}[1]{%
1054   \@namedef{cft#1fillnum}##1{%
1055     {\@nameuse{cft#1leader}}\nobreak
1056     \hb@xt@{\cftpnumwidth{\hfil}\@nameuse{cft#1pagefont}##1}\@nameuse{cft#1afterpnum}\par}}
1057
```

### 3.4 Experimental utilities

The code in this section is experimental but in the sense that the capabilities might be modified in the future rather than that the code does not work.

`\cftchapterprecis` This is experimental. `\cftchapterprecis{<text>}` typesets `<text>` at the point where it is called, and also adds `<text>` to the `.toc` file. It is expects to be called immediately after a `\chapter` command.

```
1058 \newcommand{\cftchapterprecis}[1]{%
1059   \cftchapterprecishere{#1}
1060   \cftchapterprecistoc{#1}}
```

`\cftchapterprecishere` `\cftchapterprecishere{<text>}` typesets `<text>`. It expects to be called immediately after a `\chapter` command. First add some negative vertical space to move it closer to the chapter heading.

```
1061 \newcommand{\cftchapterprecishere}[1]{%
1062   \vspace*{-2\baselineskip}}
Typeset its argument using italic font in a quote environment.
1063 \begin{quote}\textit{#1}\end{quote}
```

`\cftchapterprecistoc` `\cftchapterprecistoc{<text>}` adds `<text>` to the `.toc` file. The `<text>` will be typeset within the same margins as the the title text of a `\chapter` heading, using an italic font.

```
1064 \newcommand{\cftchapterprecistoc}[1]{\addtocontents{toc}{%
Start a group to localize changes to the paragraphing. Set the left margin to the
chapter indent plus the chapter number width.
```

```
1065   {\leftskip \cftchapindent\relax
1066     \advance\leftskip \cftchapnumwidth\relax}
```

Set the right hand margin to `\@tocrmarg`.

```
1067   \rightskip \@tocrmarg\relax
```

Typeset `<text>` using an italic font, then ensure that the paragraph is finished (to use the local skips). Finally close the group and we are done.

```
1068   \textit{#1}\protect\par}}
```

```

\cftlocalchange \cftmakelocalchange{\langle file\rangle}{\langle pnumwidth\rangle}{\langle tocrmarg\rangle} makes an entry into
\langle file\rangle to change the \cftpnumwidth and the \cfttocrmarg values.
1070 \newcommand{\cftlocalchange}[3]{%
1071   \addtocontents{\#1}{\protect\cftsetpnumwidth{\#2} \protect\cftsetrmarg{\#3}}}

\cftaddtitleline \cftaddtitleline{\langle file\rangle}{\langle kind\rangle}{\langle title\rangle}{\langle page\rangle} adds a \cftcontentsline entry
to \langle file\rangle with the given information.
1072 \newcommand{\cftaddtitleline}[4]{\addtocontents{\#1}{%
1073   \protect\cftcontentsline{\#2}{\#3}{\#4}}}

\cftaddnumtitleline \cftaddtitleline{\langle file\rangle}{\langle kind\rangle}{\langle num\rangle}{\langle title\rangle}{\langle page\rangle} adds a \cftcontentsline
entry to \langle file\rangle with the given information.
1074 \newcommand{\cftaddnumtitleline}[5]{\addtocontents{\#1}{%
1075   \protect\cftcontentsline{\#2}{\protect\cftnumberline{\#3}{\#4}{\#5}}}}

And, if dear old hyperref has been used, we have to fix up these two macros.

1076 \AtBeginDocument{%
1077   \@ifpackageloaded{hyperref}{%
1078     \renewcommand{\cftaddtitleline}[4]{\addtocontents{\#1}{%
1079       \protect\cftcontentsline{\#2}{\#3}{\#4}{\@currentHref}}}%
1080     \renewcommand{\cftaddnumtitleline}[5]{\addtocontents{\#1}{%
1081       \protect\cftcontentsline{\#2}{\protect\cftnumberline{\#3}{\#4}{\#5}{\@currentHref}}}%
1082   }{}%
1083 }%
1084

The end of this package.

1085 
```

## References

- [Coc95] Steven Douglas Cochran. *The subfigure package*. March 1995. (Available from CTAN as file `subfigure.dtx`)
- [Dru99] Jean-Pierre Drucbert. *The minitoc package*. August 1999. (Available from CTAN in subdirectory `/minitoc`)
- [GMS94] Michel Goossens, Frank Mittelbach, and Alexander Samarin. *The LaTeX Companion*. Addison-Wesley Publishing Company, 1994.
- [Lin97] Ulf A. Lindgren. *FncyChap V1.11*. April 1997. (Available from CTAN in subdirectory `/fncychap`)
- [Lin95] Anselm Lingnau. *An Improved Environment for Floats*. March 1995. (Available from CTAN in subdirectory `/float`)
- [Wil96a] Peter Williams. *Algorithms*. April 1996. (Available from CTAN in subdirectory `/algorithm`)

- [Wil96b] Peter R. Wilson. *LaTeX for standards: The LaTeX package files user manual*. NIST Report NISTIR, June 1996.
- [Wil00] Peter R. Wilson. *The tocbibind package*. March 2000. (Available from CTAN as file `tocbibind.dtx`)
- [Wil01] Peter R. Wilson. *The ccaption package*. March 2001. (Available from CTAN as file `ccaption.dtx`)

## Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

<b>Symbols</b>	986, 988, 990,	1000, 1002, 1004
\@afterheading . . . . .	992, 994, 996,	\@cftpnumon . . . 1020,
. 127, 527, 629, 901	998, 1000, 1002,	1022, 1024,
\@afterindenttrue . . . . .	1018, 1019,	1026, 1028,
. 185, 241,	1022, 1024,	1030, 1032,
287, 332, 372,	1026, 1028,	1034, 1036,
412, 452, 553,	1030, 1032,	1038, 1040, 1053
655, 692, 734, 800	1034, 1036, 1038	\@cftquit . . . 14, 27, 31
\@cftasnum . 17, 154,	\@cftaschapterfalse 23	\@cftsetindents . . .
155, 190, 246,	\@cftaschaptertrue 29	. . . . . 928, 930,
292, 337, 377,	\@cftaspartfalse . 160	932, 934, 936,
417, 457, 558,	\@cftasparttrue . 160	938, 940, 942,
660, 697, 739, 805	\@cftkomafalse . . . . . 17	944, 946, 948, 961
\@cftasnumb . 17, 154,	\@cftkomatrue . . . . . 18–20	\@cftsetsubfig . . . . .
155, 191, 247,	\@cftl@subfig . . . . .	. . . . . 706, 770, 774
293, 338, 378,	. . . . . 685, 771, 775	\@cftsetsubtab . . . . .
418, 458, 559,	\@cftl@subtab . . . . .	. . . . . 747, 770, 774
661, 698, 740, 806	. . . . . 727, 771, 775	\@cftsubfigoptfalse 47
\@cftbsnum . 17, 154,	\@cftmakeZtitle . . . 888	\@cftsubfigopttrue . 48
155, 189, 245,	\@cftmakeloftitle .	\@cfttocbibindfalse 34
291, 336, 376,	. . . . . 504, 514	\@cfttocbibindtrue . 34
416, 456, 557,	\@cftmakelottitle .	\@cfttocfinish . . . . .
659, 696, 738, 804	. . . . . 606, 616	. . . . . 70, 111,
\@cftdobiblof . 486, 506	\@cftmaketoctitle .	510, 612, 875, 885
\@cftdobiblot . 588, 608	. . . . . 105, 114	\@cfttocstart 70, 101,
\@cftdobibtoc . 84, 107	\@cftnctocfalse . . . 44	500, 602, 867, 878
\@cftdopartfalse . . . 163	\@cftnctoctrue . . . . 45	\@currentHref 1079, 1081
\@cftdoparttrue 166, 170	\@cftpagestyle . . . 52,	\@dotsep . . . . . 2
\@cftemp . . . . . 926,	121, 521, 623, 895	\@dottedtocline . . . . 4
927, 930, 932,	\@cftpnumoff . . . . .	\@eha . . . . . 792
934, 936, 938,	. . . . . 966, 984, 986,	\@highpenalty . 176, 236
940, 942, 944,	988, 990, 992,	\@ifclassloaded . . . 18–20
946, 982, 983,	994, 996, 998,	\@ifpackagelater . . . 36

```

\@ifpackageloaded . . . . . 1071, 1072, \cftbeforesubfigskip
    ..... 34, 1077 1074, 1078, 1080 ..... 688, 707
\@ifundefined . . . . . \AtBeginDocument . . \cftbeforesubparaskip
    ..... 22, 24, 160, 779, 783 . . . . . 448, 463
\@namedef . . . . . 599, 771, 773, 1076 \cftbeforesubsecskip
    ..... 794, 833–842, ..... 328, 343
    854, 859, 862, \cftbeforesubsubsecskip
    866, 877, 888, ..... 368, 383
    909, 911, 917, \cftbeforesubtabskip
    919, 922, 967, 1054 ..... 730, 748
\@nameuse . 795–797, \cftbeforetabskip
    800, 803, 808, ..... 651, 667
    809, 814, 818, \cftbeforetoctitleskip
    819, 821, 822, ..... 117, 119, 128
    824, 825, 827, \cftbeforeXskip . 9, 813
    828, 830, 831, \cftbeforeZtitleskip
    838, 843, 844, ..... 7, 903
    873, 882, 891, \cftchapafterpnum . 253
    893, 897, 898, \cftchapaftersnum .
    900, 906, 907, ..... 246, 253
    914, 915, 962, \cftchapaftersnumb .
    963, 968, 1055, 1056 ..... 247, 253
\@nobreakfalse 198, 202 \cftchapdotsep . . . . . 253
\@nobreaktrue . 197, 201 \cftchapfillnum 250, 253
\@pnumwidth . 2, 145, \cftchapfont . 249, 253
    225, 270, 324, \cftchapindent . .
    364, 404, 444, ..... 238, 241, 253, 1065
    484, 581, 683, \cftchapleader . . . . . 253
    724, 765, 844, 1056 \cftchapname . .
\@restonecalfalse . 75 ..... 927, 970, 983, 1019
\@restonecoltrue . 73 \cftchapnumwidth . .
\@secpenalty 115, 178, ..... 244, 253, 1066
    281, 515, 617, 889 \cftchappagefont . . . . . 253
\@spaces . . . . . \cftchappresnum 245, 253
\@starttoc . . . . . \cftchapterprecis . .
    109, ..... 15, 1058
    508, 610, 874, 883 \cftchapterprecishere
\@tocextra 91, 493, 595 ..... 16, 1059, 1061
\@tocrmarg . 2, 146, \cftchapterprecistoc
    183, 239, 285, ..... 16, 1060, 1064
    330, 370, 410, \cftdot . . . . . 147
    450, 551, 653, \cftdotfill . . . . . 147,
    690, 732, 798, 1067 ..... 217, 264, 309,
\A ..... 317, 358, 398,
\addcontentsline . . . . . ..... 438, 478, 575,
    ..... 2, 88, 91, ..... 677, 717, 758, 838
    490, 493, 592, 595 \cftdotsep . . . . . 150,
\addtocontents . . . . . ..... 310, 359, 399,
    ..... 4, 1064, ..... 439, 479, 576,
\cftbeforeparaskip . . . . . ..... 678, 718, 759, 837
\cftbeforepartskeep . . . . .
```

```

\cftfigafterpnum . . . . . 565 \cftparskip . . . . . 8, 95, 104, 503, 605, 881 \cftsubfigname . . . . . 942, 970, 998, 1034
\cftfigaftersnum . . . . . 558, 565 \cftpaafterpnum . . . . . 208 \cftsubfignumwidth . . . . . 695, 707
\cftfigaftersnumb . . . . . 559, 565 \cftpaaftersnum . . . . . 190, 208 \cftsubfigpagefont . . . . . 707
\cftfigdotsep . . . . . 565 \cftpaaftersnumb . . . . . 191, 208 \cftsubfigpresnum . . . . . 696, 707
\cftfigfillnum 562, 565 \cftpaaftersnumb . . . . . 191, 208 \cftsubparaaftrpnum . . . . . 463
\cftfigfont . . . . . 561, 565 \cftpaaftersnumb . . . . . 194, 208 \cftsubparaaftrsnum . . . . . 457, 463
\cftfigindent . . . . . 550, 553, 565 \cftpaaftersnumb . . . . . 193, 208 \cftsubparaaftrpnum . . . . . 458, 463
\cftfigleader . . . . . 565 \cftpaaftersnumb . . . . . 182, 185, 208 \cftsubparadotsep . . . . . 463
\cftfigname . . . . . 940, 970, 996, 1032 \cftpaaftersnumb . . . . . 188, 208 \cftsubparafillnum . . . . . 461, 463
\cftfignumwidth 556, 565 \cftpaaftersnumb . . . . . 189, 193, 208 \cftsubparafont 460, 463
\cftfigpagefont . . . . . 565 \cftpaaftersnumb . . . . . 189, 193, 208 \cftsubparaindent . . . . . 449, 452, 463
\cftfigpresnum 557, 565 \cftpaaftersnumb . . . . . 298 \cftsubparaleader . . . . . 463
\cftlocalchange 16, 1070 \cftpaaftersnumb . . . . . 292, 298 \cftsubparaname . . . . . 938, 970, 994, 1030
\cftloftitlefont . . . . . 523, 538 \cftpaaftersnumb . . . . . 293, 298 \cftsubparanumwidth . . . . . 455, 463
\cftlottitlefont . . . . . 625, 640 \cftsecdotsep . . . . . 298 \cftsubparapagefont 463
\cftmarklof . . . . . 56, 524 \cftsecfillnum 296, 298 \cftsubparapresnum . . . . . 456, 463
\cftmarklot . . . . . 56, 626 \cftsecfont . . . . . 295, 298 \cftsubsecafterpnum . . . . . 343, 364
\cftmarktoc . . . . . 56, 124 \cftsecindent . . . . . 284, 287, 298 \cftsubsecaftersnum . . . . . 337, 343
\cftmarkZ . . . . . 7, 858 \cftsecleader . . . . . 298 \cftsubsecaftersnumb . . . . . 338, 343
\cftnodots . . . . . 8, 150, 218, 265, 318 \cftsecname . . . . . 930, 970, 986, 1022 \cftsubsecdotsep . . . . . 343
\cftpagenumbersoff . . . . . 12, 981 \cftsecnumwidth 290, 298 \cftsubsecfillnum . . . . . 341, 362
\cftpagenumberson . . . . . 12, 1017 \cftsecpagefont . . . . . 298 \cftsubsecfont 340, 343
\cftpaafterpnum . . . . . 423 \cftsecpresnum 291, 298 \cftsubsecindent . . . . . 329, 332, 343
\cftpaaftersnum . . . . . 417, 423 \cftsetindents . . . . . 10, 925 \cftsubseclleader . . . . . 343, 363
\cftpaaftersnumb . . . . . 418, 423 \cftsetpnumwidth . . . . . 8, 145, 1071 \cftsubsecname . . . . . 932, 970, 988, 1024
\cftpadotsep . . . . . 423 \cftsetrmarg 8, 145, 1071 \cftsubsecnumwidth . . . . . 335, 343
\cftpafillnum 421, 423 \cftsubfigafterpnum 707 \cftsubsecpagefont . . . . . 343, 364
\cftpafont . . . . . 420, 423 \cftsubfigaftersnum . . . . . 689, 692, 707 \cftsubsecpresnum . . . . . 336, 343
\cftparaindent . . . . . 409, 412, 423 \cftsubfigaftersnumb . . . . . 698, 707
\cftpaleader . . . . . 423 \cftsubfigdotsep . . . . . 707 \cftsubfigfillnum . . . . .
\cftparaname . . . . . 936, 970, 992, 1028 \cftsubfigfont 700, 707 \cftsubfigindent . . . . .
\cftparanumwidth . . . . . 415, 423 \cftsubfigpresnum . . . . . 689, 692, 707 \cftsubfigleader . . . . . 707
\cftpapagefont . . . . . 423
\cftpapresnum 416, 423
\cftparfillskip 152, 968

```

\cftsubsubseafterpnum	\cfttabindent	484, 581, 683,
.....	..... 652, 655, 667	724, 765, 844, 1056
\cftsubsubseafersnum	\cfttableader	\Huge .....
.....	..... 667	138,
\cftsubsubseafersnumb	\cfttabname	539, 641, 911, 919
.....	944, 970, 1000, 1036	
\cftsubsubsecfont	\cfttabnumwidth	<b>I</b>
.....	658, 667	\if@bibchapter .....
\cftsubsubsecdotsep	\cfttabpagefont	..... 86, 488, 590
\cftsubsubsecfillnum	\cfttabpresnum	\if@cfwdopart .....
.....	659, 667	158
\cftsubsubsecfont	\cfttictitlefont	\if@cfthaschapter 14,
.....	..	71, 79, 116, 130,
\cftsubsubsecindent	\cftXafterpnum	137, 165, 169,
....	10, 833	175, 196, 233,
\cftsubsubsecleader	\cftXaftersnum	253, 278, 304,
\cftsubsubsecname	\cftXdotsep	347, 387, 427,
.	10, 833	467, 516, 531,
934, 970, 990, 1026	\cftXfillnum	538, 618, 633,
\cftsubsubsecnumwidth	\cftXfont	640, 868, 890, 905
.....	9, 833	
\cftsubsubsecpagefont	\cftXindent	\if@cfthaspart .....
.....	9, 815	..... 159, 161, 208
\cftsubsubsecpresnum	\cftXleader	\if@cftkoma .....
.....	10, 833	... 16, 62, 139,
\cftsubtabafterpnum	\cftXnumwidth	142, 226, 271,
748	9, 815	540, 543, 642,
\cftsubtabaftersnum	\cftXpagefont	645, 858, 908, 916
.....	10, 833	
\cftsubtabaftersnumb	\cftXpresnum	\if@cftnctoc .....
.....	9, 833	44, 99, 498, 600, 865
\cftsubtabdotsep	\cftZtitlefont	\if@cftsubfigopt ..
...	7, 903	. 47, 583, 769, 773
\cftsubtabfillnum	\chapter	\if@cfttocbibind ..
.	869	. 32, 106, 505, 607
.....	\contentsline	\if@compatibility .. 200
743, 748	2, 1073,	\if@dotoclof .....
\cftsubtabfont	1075, 1079, 1081	487
742, 748	\contentsname	\if@dotoclot .....
\cftsubtabindent	.....	589
..	57, 64, 88, 91, 123	\if@dotoc toc .....
....	\csname	85
731, 734, 748	787, 788,	\if@restonecol .....
\cftsubtableader	804–806, 813,	80
.. 748	815, 816, 903, 904	\if@twocolumn .....
\cftsubtabname	\endcsname	72
....	787, 788,	\interlinepenalty ..
946, 970, 1002, 1038	804–806, 813,	. 122, 186, 242,
\cftsubtabnumwidth	815, 816, 903, 904	288, 333, 373,
.....	\endinput	413, 453, 522,
737, 748	27	554, 624, 656,
\cftsubtabpagefont	\extoz	693, 735, 801, 896
.. 748	..... 854	
\cftsubtabpresnum	\GenericWarning	<b>G</b>
.....	.... 5	<b>L</b>
\cfttabaftersnum	\Huge	\l@ ... . 811
.....	.....	\l@chapter .....
\cfttabdotsep	\hb@xt@	233
.....	..... 154,	\l@figure .....
\cfttabfillnum	225, 270, 324,	547
664, 667	364, 404, 444,	\l@paragraph .....
\cfttabfont		406
.. 663, 667		\l@part .....
		158

\l@section . . . . .	276	N	\phantomsection . . . . .
\l@subfigure . . . . .	686	\newif . . . . .	15, 16, . . . . .
\l@subparagraph . . . . .	446	32, 44, 47, 158, 159	82, 87, 90, . . . . .
\l@subsection . . . . .	326	\newlistentry . . . . .	489, 492, 591, 594
\l@subsubsection . . . . .	366	. . . . .	\videocommand 4, 11,
\l@subtable . . . . .	728	13, <u>778</u> , 849, 851	70, 78, 82, 147,
\l@table . . . . .	649	\newlistof . . . . .	148, 150, 721, 762
\l@X . . . . .	14, <u>794</u>	\noexpand . . . . .	\ProvidesPackage . . . . .
\Large . . . . .	141, 542, 644	788	3
\large . . . . .	213, 217, 219, 228, 229	\normalfont . . . . .	\PRWPackageNote . . . . .
\leaders . . . . .	149	138, 141, 308, 309, 311, 354, 358, 360, 394, 398, 400, 434, 438, 440, 474, 478, 480, 539, 542, 571, 575, 577, 641, 644, 673, 677, 679, 713, 717, 719, 754, 758, 760, 833, 838, 839, 911, 919	\PRWPackageNoteNoLine . . . . .
\leftskip . . . . .	182, 192, 238, 248, 284, 294, 329, 339, 369, 379, 409, 419, 449, 459, 550, 560, 652, 662, 689, 699, 731, 741, 797, 807, 1065, 1066	\numberline . . . . .	4, 28, 30
\listfigurename . . . . .	59, 66, 490, 493, 523	O	S
\listoffigures . . . . .	6, <u>497</u>	\onecolumn . . . . .	\sectfont . . . . .
\listoftables . . . . .	6, <u>599</u>	P	139, 142, 228, 229, 272, 540, 543, 642, 645, 909, 917
\listofX . . . . .	13, <u>865</u>	\PackageError . . . . .	\section . . . . .
\listtablename . . . . .	61, 68, 592, 595, 625	\PackageWarning . . . . .	871
\lofdepth . . . . .	583	\parindent . . . . .	\size@chapter . . . . .
\lotdepth . . . . .	583	. . . . .	. . . . . 139, 540, 642, 909
M		104, 185, 241, 287, 332, 372, 412, 452, 503, 553, 605, 655, 692, 734, 800, 881	\size@section . . . . .
\MakeUppercase . . . . .	57, 59, 61, 863	\parskip . . . . .	. . . . . 142, 543, 645, 917
\MessageBreak . . . . .	38–40	. . . . .	T
\mkern . . . . .	149		\tableofcontents . . . . .
Z			6, <u>98</u>
			\textit . . . . .
			1063, 1068
			\theX . . . . .
			<u>14</u> , <u>779</u>
			\thispagestyle . . . . .
			53
			\toclevel@subfig . . . . .
			<u>707</u>
			\toclevel@subfigure . . . . .
			687, 721
			\toclevel@subtable . . . . .
			729, <u>748</u>
			\toclevel@X . . . . .
			<u>841</u>
			\tocloftpagestyle . . . . .
			6, <u>52</u>
			\twocolumn . . . . .
			80
			Z
			\Zdepth . . . . .
			<u>13</u> , <u>854</u>